



A powerful lockdown solution for fixed-function computers



Trend Micro Incorporated reserves the right to make changes to this document and to the product described herein without notice. Before installing and using the product, review the readme files, release notes, and/or the latest version of the applicable documentation, which are available from the Trend Micro website at:

http://docs.trendmicro.com/en-us/enterprise/trend-micro-safe-lock.aspx

© 2015 Trend Micro Incorporated. All Rights Reserved.Trend Micro, the Trend Micro t-ball logo, Trend Micro Safe Lock, Safe Lock Intelligent Manager, Trend Micro Portable Security, Trend Micro Portable Security 2, and TrendLabs are trademarks or registered trademarks of Trend Micro Incorporated. All other product or company names may be trademarks or registered trademarks of their owners.

Document Part No.: SLEM26987/150615

Release Date: July 2015

Protected by U.S. Patent No.: Patents pending.

This documentation introduces the main features of the product and/or provides installation instructions for a production environment. Read through the documentation before installing or using the product.

Detailed information about how to use specific features within the product may be available at the Trend Micro Online Help Center and/or the Trend Micro Knowledge Base.

Trend Micro always seeks to improve its documentation. If you have questions, comments, or suggestions about this or any Trend Micro document, please contact us at docs@trendmicro.com.

Evaluate this documentation on the following site:

http://docs.trendmicro.com/en-us/survey.aspx



Table of Contents

Preface

Preface	. v
About the Documentation	. v
Audience	vi
Document Conventions	vi

Chapter 1: Introduction

About Trend Micro Safe Lock	1-2
What's New in This Version	1-2
Agent Features and Benefits	1-3
Safe Lock Requirements	1-4
Agent Use Overview	1-10

Chapter 2: Using the Agent Console

Setting Up the Approved List	2-2
About the Agent Console	2-5
About Status Icons	2-7
About the Approved List About Hashes Configuring the Approved List	
Account Types	2-15
Configuring Passwords	2-16
About Feature Settings	2-17
Enabling or Disabling Feature Settings	2-19

Chapter 3: Using the Agent Command Line Interface (CLI)

Using SLCmd at the Command Line Interface (CLI)	3-2
SLCmd Program and Console Function Comparison	3-2
SLCmd Program Commands	3-3

i.

Chapter 4: Working with the Agent Configuration File

Working with the Agent Configuration File	4-2
Changing Advanced Settings	4-2
Configuration File Syntax	4-3
Configuration File Parameters	4-7

Chapter 5: Troubleshooting

Frequently Asked Questions (FAQ)	5-2
What if the endpoint becomes infected by a threat?	5-2
Where can I get more help with Trend Micro Safe Lock?	5-2
Troubleshooting Safe Lock	5-2
0	
Using the Diagnostic Toolkit	5-5

Chapter 6: Technical Support

Troubleshooting Resources	6-2
Using the Support Portal	6-2
Trend Community	6-2
Contacting Trend Micro	6-3
Speeding Up the Support Call	6-3
Other Resources	6-4
TrendEdge	6-4
Download Center	6-4
TrendLabs	6-5

Chapter 7: Appendix: Reference

Enabling Local Administrator Accounts	7-2
Enabling Local Accounts for Default Shares	7-3
Agent Event Log Descriptions	7-4
Agent Error Code Descriptions	7-25

ii

Index

Index IN-1



Preface

This Administrator's Guide introduces Trend Micro Safe Lock and guides administrators through installation and deployment.

Topics in this chapter include:

- About the Documentation on page v
- Audience on page vi
- Document Conventions on page vi

About the Documentation

Trend Micro Safe Lock documentation includes the following:

TABLE 1. Trend	Micro Saf	e Lock Do	cumentation
----------------	-----------	-----------	-------------

DOCUMENTATION	DESCRIPTION
Installation Guide	A PDF document that discusses requirements and procedures for installing Safe Lock.
Administrator's Guide	A PDF document that discusses getting started information and Safe Lock usage and management.
Readme file	Contains a list of known issues. It may also contain late- breaking product information not found in the printed documentation.
Knowledge Base	An online database of problem-solving and troubleshooting information. It provides the latest information about known product issues. To access the Knowledge Base, go to the following website:
	http://esupport.trendmicro.com

Download the latest version of the PDF documents and Readme at:

http://docs.trendmicro.com

Audience

Trend Micro Safe Lock documentation is intended for administrators responsible for Safe Lock management, including agent installation.

Document Conventions

The following table provides the official terminology used throughout the Trend Micro Safe Lock documentation:

CONVENTION	DESCRIPTION
UPPER CASE	Acronyms, abbreviations, and names of certain commands and keys on the keyboard
Bold	Menus and menu commands, command buttons, tabs, and options
Italics	References to other documents
Monospace	Sample command lines, program code, web URLs, file names, and program output
Navigation > Path	The navigation path to reach a particular screen
	For example, File > Save means, click File and then click Save on the interface
Note	Configuration notes
Tip Tip	Recommendations or suggestions
Important	Information regarding required or default configuration settings and product limitations

TABLE 2. Document Conventions

CONVENTION	DESCRIPTION
WARNING!	Critical actions and configuration options



Chapter 1

Introduction

Trend Micro Safe Lock delivers a simple, no-maintenance solution to lock down and protect fixed-function computers, helping protect businesses against security threats and increase productivity.

Topics in this chapter include:

About Trend Micro Safe Lock on page 1-2



About Trend Micro Safe Lock

Trend Micro Safe Lock protects fixed-function computers like Industrial Control Systems (ICS), Point of Sale (POS) terminals, and kiosk terminals from malicious software and unauthorized use. By using fewer resources and without the need for regular software or system updates, Safe Lock can reliably secure computers in industrial and commercial environments with little performance impact or downtime.

What's New in This Version

This section lists the new features and enhancements available in each release.

Trend Micro Safe Lock 2.0 Features and Enhancements

Trend Micro Safe Lock 2.0 includes the following new features and enhancements.

FEATURE	DESCRIPTION
Write Protection	Prevents write access to all files in the Approved List and all objects (files, folders, and registry entries) in the Write Protection List
Integrity Monitoring	Monitors file change events system-wide for files, folders, and the registry
Approved List and Trusted Updater support Digital Signatures	Allow to loading or launching files that have pre-defined digital signatures, even if the files are not in the Approved List
Exception Path	Allow to loading or launching files in a pre-defined "exceptions" folder without adding them to the Approved List
Custom Action	Takes action on blocked files, for example Ignore, Quarantine, or Ask Server (requires Safe Lock Intelligent Manager)

TABLE 1-1. New Features

Agent Features and Benefits

Trend Micro Safe Lock includes the following features and benefits.

Application Lockdown

By preventing programs, DLL files, drivers, and scripts not specifically on the Approved List of applications from running (also known as application white listing), Safe Lock provides both improved productivity and system integrity by blocking malicious software and preventing unintended use.

Safe Lock write protection blocks modification and deletion of files, folders, and registry entries.

Exploit Prevention

Known targeted threats like Downad and Stuxnet, as well as new and unknown threats, are a significant risk to ICS and kiosk computers. Systems without the latest operating system updates are especially vulnerable to targeted attacks.

Safe Lock provides both intrusion prevention, which helps prevent threats from spreading to the endpoint, and execution prevention, which helps prevent threats from spreading to the endpoint or from running.

Easy Management

When software needs to be installed or updated, the Trusted Updater and Predefined Trusted Updater List provide an easy way to make changes to the endpoint and automatically add new or modified files to the Approved List, all without having to unlock Trend Micro Safe Lock.

Small Footprint

Compared to other endpoint security solutions that rely on large pattern files that require constant updates, application lockdown uses less memory and disk space, without the need to download updates.

Role Based Administration

Trend Micro Safe Lock provides a separate administrator and Restricted User account, providing full control during installation and setup, as well as simplified monitoring and maintenance after deployment.

Graphical and Command Line Interfaces

Anyone who needs to check the software can use the console, while system administrators can take advantage of the command line interface (CLI) to access all of the features and functions available.

Trend Micro Portable Security Compatible

Out-of-the-box compatibility with Trend Micro Portable Security ensures straightforward removal of any threats that do get on to the endpoint, without the need to update the Approved List or unlock the endpoint.

Self Protection

Self Protection provides ways for Trend Micro Safe Lock to defend the processes and other resources required to function properly. Self Protection helps thwart attempts by programs or actual users to disable the software.

Self Protection blocks all attempts to terminate the following services:

- Trend Micro Safe Lock Service (WkSrv.exe)
- Trend Micro Unauthorized Change Prevention Service (TMBMSRV.exe)
- Trend Micro Personal Firewall (TmPfw.exe)

Safe Lock Requirements

1 - 4

This section introduces Safe Lock system requirements and upgrade limitations.

Hardware Requirements

Trend Micro Safe Lock does not have specific hardware requirements beyond those specified by the operating system, with the following exceptions:

TABLE 1-2. Required Hardware for Safe Lock

Hardware/Software	DESCRIPTION
Available disk space	200MB minimum
	300MB recommended
Monitor resolution	640x480

Important

Safe Lock cannot be installed on a system that already runs one of the following:

- Trend Micro OfficeScan
- Trend Micro Titanium
- Another Trend Micro endpoint solution

Operating Systems

Note 👔

Memory Randomization, API Hooking Prevention, and DLL Injection Prevention are not supported on 64-bit platforms.

WINDOWS VERSION TYPE	WINDOWS VERSION NAME		
Windows Clients	Windows 2000 SP4* (32-bit)		
	Note *Without Update Rollup, this version of Windows does not support DLL/Driver Lockdown, Integrity Monitoring, and the Predefined Trusted Updater.		
	Windows XP SP1*/SP2/SP3 (32-bit) (except Starter and Home editions)		
	Note		
	*This version of Windows does not support DLL/Driver Lockdown, Integrity Monitoring, and the Predefined Trusted Updater.		
	Safe Lock does not support a custom action of "quarantine" on Windows XP or Windows 2003.		
	Windows Vista No-SP/SP1/SP2 (32-bit) (except Starter and Home editions)		
	Windows 7 No-SP/SP1 (32-bit and 64-bit) (except Starter and Home editions)		
	Windows 8 No-SP (32-bit and 64-bit)		
	Windows 8.1 No-SP (32-bit and 64-bit)		

TABLE 1-3. List of Supported Operating Systems

WINDOWS VERSION TYPE	WINDOWS VERSION NAME
Windows Server	Windows 2000 Server SP4* (32-bit)
	Note *Without Update Rollup, this version of Windows does not support DLL/Driver Lockdown, Integrity Monitoring, and the Predefined Trusted Updater.
	Windows Server 2003 SP1/SP2 (32-bit)
	Note Safe Lock does not support a custom action of "quarantine" on Windows XP or Windows 2003.
	Windows Server 2003 R2 No-SP/SP2 (32-bit and 64-bit)
	Note Safe Lock does not support a custom action of "quarantine" on Windows XP or Windows 2003.
	Windows Server 2008 SP1/SP2 (32-bit and 64-bit)
	Windows Server 2008 R2 No-SP/SP1 (64-bit)
	Windows Server 2012 No-SP (64-bit)
	Windows Server 2012 R2 No-SP (64-bit)

WINDOWS VERSION TYPE	WINDOWS VERSION NAME
Windows Embedded Standard	Windows (Standard) XP Embedded SP1*/SP2 (32-bit)
	Note
	*This version of Windows does not support DLL/Driver Lockdown, Integrity Monitoring, and the Predefined Trusted Updater.
	Safe Lock does not support a custom action of "quarantine" on Windows XP or Windows 2003.
	Windows Embedded Standard 2009 (32-bit)
	Windows Embedded Standard 7 (32-bit and 64-bit)
	Windows Embedded Standard 8 (32-bit and 64-bit)
	Windows Embedded Standard 8.1 (32-bit and 64-bit)
Windows Embedded	Windows Embedded POSReady (32-bit)
POSReady	Windows Embedded POSReady 2009 (32-bit)
	Windows Embedded POSReady 7 (32-bit and 64-bit)
Windows Embedded Enterprise	Windows Embedded Enterprise XP SP1*/SP2/SP3 (32-bit)
	Note
	*This version of Windows does not support DLL/Driver Lockdown, Integrity Monitoring, and the Predefined Trusted Updater.
	Safe Lock does not support a custom action of "quarantine" on Windows XP or Windows 2003.
	Windows Embedded Enterprise Vista (32-bit)
	Windows Embedded Enterprise 7 (32-bit and 64-bit)

WINDOWS VERSION TYPE	WINDOWS VERSION NAME
Windows Embedded Server	Windows Embedded Server 2003 SP1/SP2 (32-bit)
	Note
	Safe Lock does not support a custom action of "quarantine" on Windows XP or Windows 2003.
	Windows Embedded Server 2003 R2 (32-bit)
	Note
Safe Loc "quarant	Safe Lock does not support a custom action of "quarantine" on Windows XP or Windows 2003.
	Windows Embedded Server 2008 (32-bit and 64-bit)
	Windows Embedded Server 2008 R2 (64-bit)
	Windows Embedded Server 2012 (64-bit)
	Windows Embedded Server 2012 R2 (64-bit)

Note

See the latest Safe Lock readme file for the most up-to-date list of supported operating systems for agents.

Agent Upgrade Preparation

WARNING!

Depending on the installation method you select, Safe Lock versions require different preparation before upgrading.

Download the latest updates from the Trend Micro Software Download Center. Go to <u>http://downloadcenter.trendmicro.com/</u>.

Before upgrading, take the appropriate action below for your installation method and installed Safe Lock agent version:

INSTALLATION METHOD	Installed Agent Version	REQUIRED ACTION	Settings Retained
Local installation using Windows Installer	1.0	No preparation needed	No settings retained
	1.1	No preparation needed	Compatible settings retained
	2.0 or later	No preparation needed	No settings retained
Local installation using Command Line Interface Installer	1.0	Manually uninstall	No settings retained
	1.1	No preparation needed	Compatible settings retained
	2.0 or later	Manually uninstall	No settings retained
Remote	1.0	Manually uninstall	No settings retained
Note Remote Safe Lock	1.1	Manually uninstall	No settings retained
Safe Lock Intelligent Manager.	2.0 or later	Manually uninstall	No settings retained

TABLE 1-4. Upgrade Actions Required by Installation Method and Installed Agent Version

Agent Use Overview

Trend Micro Safe Lock is a whitelist solution that locks down computers, preventing all applications not on the Approved List from running. Safe Lock can be configured and maintained using the graphical user interface (GUI) agent console or the command line interface (CLI). System updates can be applied without turning off Application Lockdown at the endpoint through the Predefined Trusted Updater List or by using the Trusted Updater.

Consider this typical use case scenario:

- 1. Set up the Approved List and turn on Application Lockdown on the endpoint so that unapproved applications cannot be run.
- 2. Use the Trusted Updater to update or install software whose installer is not on the Predefined Trusted Updater list.
- 3. Configure and enable the Restricted User account for later maintenance.

If someone tries to run an application not specifically on the Approved List, the following message displays:



FIGURE 1-1. Trend Micro Safe Lock blocking message



Chapter 2

Using the Agent Console

This chapter describes how to configure Trend Micro Safe Lock using the agent console on the endpoint.

Topics in this chapter include:

- Setting Up the Approved List on page 2-2
- About the Agent Console on page 2-5
- About the Approved List on page 2-8
- Account Types on page 2-15
- About Feature Settings on page 2-17

Setting Up the Approved List

Before Trend Micro Safe Lock can protect the endpoint, it must check the endpoint for existing applications and installers necessary for the system to run correctly.

Procedure

1. Open the Safe Lock console.

The Safe Lock log on screen appears.

rend Micro Safe Lock		
Safe Lock		
Password:		
1		Log On
-License Managen	nent	1997 S
License Type:	Full	
License Status:	Activated	
Expiration Date:	Unlimited	Use New Code
		Cancel

2. Provide the password and click Login.

Safe Lock asks if you want to set up the Approved List now.



2-2

3. At the notification window, select **Yes. Set up the Approved List now** and click **OK**.

Safe Lock scans the endpoint and adds all applications to the Approved List.



Safe Lock displays the Approved List Configuration Results.

Trend Micro Safe Lock				
Approved List Configuration Results				
Applications added:	Applications added: 18287			
Applications not added: 0				
Application	File Path 🔺	Results		
autoexec.bat	C:\autoexec.bat	Success		
config.sys	C:\config.sys	Success		
dao360.dll	C:\Program Files\Common Files\micros	Success		
Microsoft.Ink.dll	C:\Program Files\Common Files\micros	Success		
Microsoft.Ink.dll	C:\Program Files\Common Files\micros	Success		
tipresx.dll.mui	C:\Program Files\Common Files\micros	Success		
tipresx.dll.mui	C:\Program Files\Common Files\micros	Success		
ConvertInkStore.exe	C:\Program Files\Common Files\micros	Success		
tipresx.dll.mui	C:\Program Files\Common Files\micros	Success		
tipresx.dll.mui	C:\Program Files\Common Files\micros	Success		
tipresx.dll.mui	C:\Program Files\Common Files\micros	Success		
Le m ·		2	<u> </u>	
		Close		

🔏 Note

When Trend Micro Safe Lock Application Lockdown is on, only applications that are in the Approved List will be able to run.

4. Click Close.

About the Agent Console

The agent console provides easy access to commonly used features in Trend Micro Safe Lock.

)verview 👌	Application	Lockdown On
Approved List	This system is are in the App	only able to access applications that roved List.
Password		
Settings		Turn Application Lockdown Off
A <u>b</u> out		÷
	Application Lockdown on since:	10/2/2014 3:15:49 AM
	Exploit Prevention:	Enabled
	Number of approved applications:	<u>0</u>
	Approved List last updated on:	<u>N/A</u>

FIGURE 2-1. The Safe Lock console

The following table describes the features available on the console:

TABLE 2-1. Console Feature Descriptions

#	Ітем	DESCRIPTION	
1	Overview	Display the software status	
	Approved List	Display applications allowed to run and let users manage the list	
	Password	Change the Safe Lock administrator or Restricted User passwords (only available to administrators)	
	Settings	Enable or disable vulnerability protection settings and export or import the system configuration	
	About	Display the product and component version numbers	
2	Status information	The current status of the software	
3	3 Turn Application Lockdown On Lock down the system, blocking application the Approved List from running		
	Turn Application Lockdown Off	Release the system from lock down, allowing applications not on the Approved List to run	
		Note After disabling Lockdown mode, Safe Lock switches to a "monitor" mode. Safe Lock does not block any applications from running, but logs when applications that are not in the Approved List run. You can use these logs to assess if the Approved List contains all the applications required on the endpoint.	
4	Application Lockdown on since	The date and time that Application Lockdown was last turned on	
	Application Lockdown off since	The date and time that Application Lockdown was last turned off	

#	Ітем	DESCRIPTION
5	Exploit Prevention	Enabled : All Exploit Prevention features are enabled
		Click the status to open the settings screen.
		Enabled (Partly) : Some Exploit Prevention features are enabled
		Click the status to open the settings screen.
		Disabled : No Exploit Prevention features are enabled
		Click the status to open the settings screen.
6	Approved List status	Click the number of Approved List items or last updated date to open the Approved List.
		Click the last application blocked date to open the Blocked Application Event Log.
7	License expires on	The time and date that the software expires
		Click the date to provide a new Activation Code.

About Status Icons

Use the status icons for a visual indication of the current status of Safe Lock.

Note System Tray icons display if they were enabled during installation.

TABLE 2-2. Status Icon Descriptions

CONSOLE ICON	System Tray Icon	Status	DESCRIPTION
	•	Locked	The Approved List is being enforced. Unauthorized applications cannot be run.
		Unlocked	The Approved List is not being enforced. Unauthorized applications can be run.
N/A		Expired	When the Safe Lock license has expired, the system cannot be locked. Update the Activation Code by clicking on the expiration date.

About the Approved List

Use the Approved List to display the files that Safe Lock allows to run or make changes to the endpoint.

-			- Oncont <u>E</u>		s riuon
	Application	Full Path 🔺	Date	Hash Match	H⊸
	autoexec.bat	C:\autoexec.bat	7/6/2015 4:30:1		e
	bootmgr.exe.mui	C:\Boot\cs-CZ\bootmgr.exe.mui	7/6/2015 4:30:1		b
	bootmgr.exe.mui	C:\Boot\da-DK\bootmgr.exe.mui	7/6/2015 4:30:1		e
	bootmgr.exe.mui	C:\Boot\de-DE\bootmgr.exe.mui	7/6/2015 4:30:1		6
	bootmgr.exe.mui	C:\Boot\el-GR\bootmgr.exe.mui	7/6/2015 4:30:1		5
	bootmgr.exe.mui	C:\Boot\en-US\bootmgr.exe.mui	7/6/2015 4:30:1		4
	memtest.exe.mui	C:\Boot\en-US\memtest.exe.mui	7/6/2015 4:30:1		1
	bootmgr.exe.mui	C:\Boot\es-ES\bootmgr.exe.mui	7/6/2015 4:30:1		5
	bootmgr.exe.mui	C:\Boot\fi-FI\bootmgr.exe.mui	7/6/2015 4:30:1		е
	bootmgr.exe.mui	C:\Boot\fr-FR\bootmgr.exe.mui	7/6/2015 4:30:1		7
	bootmgr.exe.mui	C:\Boot\hu-HU\bootmgr.exe.mui	7/6/2015 4:30:1		с
Π	bootmar exe mui	C:\Boot\it-IT\bootmar exe mui	7/6/2015 4:30:1		6 -
• Numb	er of approved applic	ations: 17140 Numbe	r of applications sele	cted: 0	

FIGURE 2-2. The Safe Lock Approved List

The following table describes the features available on the Approved List.

TABLE 2-3. Approved List Item Descriptions

#	Ітем	DESCRIPTION
1	Add Item/Delete Item	Adds or removes selected items to or from the Approved List.
2	Search bar	Searches the Application and File Path columns.
3	Check Hash/Update Hash	Checks or updates the hash values for applications in the Approved List.
4	Export/Import	Exports or imports the Approved List using a SQL database (.db) file.
5	Copy to Clipboard	Copies the Approved List to the clipboard in the comma separated values (CSV) format for easy review or reporting.

About Hashes

Trend Micro Safe Lock calculates a unique hash value for each file in the Approved List. This value can be used to detect any changes made to a file, since any change results in a different hash value. Comparing current hash values to previous values can help detect file changes.

The following table describes the hash check status icons.

Ісон	DESCRIPTION
	The calculated hash value matches the stored value.
\mathbf{x}	The calculated hash value does not match the stored value.
?	There was an error calculating the hash value.

TABLE 2-4. Hash Check Status Icons

Moving or overwriting files manually (without using the Trusted Updater) can result in the hash values not matching, but the mismatch could result from other applications (including malware) altering or overwriting existing files. If unsure why a hash value mismatch has occurred, scan the endpoint for threats with Trend Micro Portable Security.

Checking or Updating Hashes

Checking the hash value of files in the Approved List can help verify the integrity of files currently permitted to run.

Procedure

- Open the Trend Micro Safe Lock console using the desktop icon (if available) or the Start menu by clicking All Programs > Trend Micro Safe Lock.
- 2. Provide the password and click Login.

3. Click the Approved List menu item to open the list.

To check the file hash values:

- a. Select the files to check. To check all files, select the check box at the top of the Approved List.
- b. Click Check Hash.

To update the file hash values:

- a. Select the files to update.
- b. Click Update Hash.

Important

If unsure why a hash value mismatch has occurred, scan the endpoint for threats.

Configuring the Approved List

After setting up the Approved List, users can add new programs by clicking **Add Item**, which displays the options in the following table.

TABLE 2-5. Metho	Is for Adding	Applications t	o the Approved List
------------------	---------------	----------------	---------------------

ΟρτιοΝ	When to Use
Manually browse and select files	Choose this option when the software already exists on the endpoint and is up-to-date. Adding a file grants permission to run the file, but does not alter the file or the system.
	For example, if Windows Media Player (wmplayer.exe) is not in the Approved List after initial setup, users can add it to the list using the console.

Ορτιον	WHEN TO USE
Automatically add files created or modified by the selected application installer (Trusted Updater)	Choose this option to open the Trusted Updater when updating the endpoint or installing new software. For example, if Mozilla Firefox needs to be installed or updated, use the Trusted Updater. Trend Micro Safe Lock adds or updates any files modified by an installer to the Approved List.

Adding or Removing Files

Procedure

- Open the Trend Micro Safe Lock console using the desktop icon (if available) or the Start menu by clicking All Programs > Trend Micro Safe Lock.
- 2. Provide the password and click Login.
- 3. Click the Approved List menu item to open the list.

To add an item:

- a. Click Add Item, select Manually browse and select files, and click Next.
- b. In the window that opens, choose Specific applications, All applications in folders and subfolders, or All applications in a folder from the drop-down list.

A selection window appears.

- c. Select the desired application or folder to add, and click **Open** or **OK**.
- d. Click **OK**. Confirm the items to be added, and click **Approve**.
- e. After adding the desired items to the Approved List, click Close.

To remove an item:

- a. Search the Approved List for the application to remove.
- b. Select the check box next to the file name to be removed, and click **Delete Item**.
- c. When asked to remove the item, click OK.
- d. Click **OK** again to close the confirmation window.

Updating or Installing Using the Trusted Updater

Trend Micro Safe Lock automatically adds applications to the Approved List after the Trusted Updater adds or modifies the program files.

Procedure

- Open the Trend Micro Safe Lock console using the desktop icon (if available) or the Start menu by clicking All Programs > Trend Micro Safe Lock.
- 2. Provide the password and click Login.
- 3. Click the **Approved List** menu item to open the list.
- **4.** To install or update an application, select the installer that the Trusted Updater should temporarily allow to run:
 - a. Click Add Item, select Automatically add files created or modified by the selected application installer, and click Next.
 - b. In the window that opens, choose File, Folder, or Folder and sub folders from the drop-down list.
 - c. Select the desired installation package or folder to add, and click **Open**.

Mote 📝

Only existing EXE, MSI, BAT, and CMD files can be added to the Trusted Updater.

d. Check that the correct items appear on the list, and click **Start**.

The Safe Lock Trusted Updater window displays.



FIGURE 2-3. The Safe Lock Trusted Updater

- 5. Install or update the program as usual. When finished, click **Stop** on the Trusted Updater.
- 6. Check that the correct items appear on the Approved List, and click **Approve**, and then click **Close**.

Exporting or Importing the Approved List

Users can export or import the as a database (.db) file for reuse in mass deployment situations. **Copy to Clipboard** creates a CSV version of the list on the Windows clipboard.



WARNING!

The operating system files used by the exporting and importing endpoints must match exactly. Any difference between the operating system files on the endpoints can lead to operating system malfunctions or system lock-out after importing.

Procedure

- Open the Trend Micro Safe Lock console using the desktop icon (if available) or the Start menu by clicking All Programs > Trend Micro Safe Lock.
- 2. Provide the password and click Login.
- 3. Click the Approved List menu item to open the list.

To export the Approved List:

- a. Click **Export**, and choose where to save the file.
- b. Provide a filename, and click Save.

To import an Approved List:

- a. Click **Import**, and locate the database file.
- b. Select the file, and click **Open**.

Account Types

Trend Micro Safe Lock provides role-based administration, allowing administrators to grant users access to certain features on the main console. Through the configuration file, Safe Lock administrators can specify the features available to the Restricted Users account.

TABLE 2-6. Safe Lock Accounts

Ассоинт	DETAILS	
Administrator	Default account	
	Full access to Safe Lock functions	
	Can use both the console and command line interface (CLI)	

Ассоинт	DETAILS	
Restricted User	Secondary maintenance account	
	Limited access to Safe Lock functions	
	Can only use the console	

To enable the Restricted User account, see *Configuring Passwords on page 2-16*. To sign in with a specific account, specify the password for that account.

Configuring Passwords

While the Safe Lock administrator and Restricted User passwords can be changed from the console, only the administrator can change passwords. To log on the console as the administrator account, provide the administrator password when launching the console.



Important

The Safe Lock administrator and Restricted User passwords cannot be the same.

Procedure

- Open the Trend Micro Safe Lock console using the desktop icon (if available) or the Start menu by clicking All Programs > Trend Micro Safe Lock.
- 2. Provide the Safe Lock administrator password and click Login.
- 3. Click the **Password** menu item to display the administrator password page.

To change the Safe Lock administrator password:

a. Provide the current password, specify and confirm the new password, and click **Save**.



WARNING!

The only way to recover after losing the Safe Lock administrator password is by reinstalling the operating system.

To create a Restricted User password:

- a. Click **Restricted User** at the top of the console.
- b. Select the **Use Restricted User** check box.
- c. Specify and confirm the password, and click Save.

To change an existing Restricted User password:

a. Specify and confirm the new password, and click Save.

About Feature Settings

Safe Lock offers the following protection features.



FIGURE 2-4. Safe Lock settings screen

TABLE 2-7. Intrusion Prevention

Setting	DESCRIPTION	
USB Malware Protection	USB Malware Protection prevents automated threats on USB or remote drives from infecting the endpoint. Just viewing the contents of the drive may be enough to pass along an infection.	
	Enable this feature to prevent files on USB devices from automatically infecting the endpoint.	
Network Virus Protection	 Network Virus Protection scans incoming and outgoing network traffic, blocking threats from infected computers or other devices on the network. 	
	Enable this feature to prevent threats on the network from infecting the endpoint.	

TABLE 2-8. Execution Prevention

Setting	DESCRIPTION	
Memory Randomization	Address Space Layout Randomization helps prevent shellcode injection by randomly assigning memory locations for important functions, forcing an attacker to guess the memory location of specific processes.	
	Enable this feature on older operating systems such as Windows XP or Windows Server 2003, which may lack or offer limited Address Space Layout Randomization (ASLR) support.	
	Note The endpoint must be restarted to enable or disable Memory Randomization.	
DLL Injection Prevention	DLL Injection Prevention detects and blocks API call behaviors used by malicious software. Blocking these threats helps prevent malicious processes from running.	
	Never disable this feature except in troubleshooting situations since it protects the system from a wide variety of serious threats.	

Setting	DESCRIPTION	
API Hooking Prevention	API Hooking Prevention detects and blocks malicious software that tries to intercept and alter messages used in critical processes within the operating system.	
	Never disable this feature except in troubleshooting situations since it protects the system from a wide variety of serious threats.	

TABLE 2-9. Application Lockdown

Setting	DESCRIPTION	
DLL/Driver Lockdown	DLL/Driver Lockdown prevents unapproved DLLs or drivers from being loaded into the memory of protected endpoints.	
Script Lockdown	Script Lockdown prevents unapproved script files from being run on protected endpoints.	
Write Protection	Write Protection prevents write access to objects (files, folders, and registry entries) in the Write Protection List and optionally prevents write access to files in the Approved List.	

TABLE 2-10. Other

Setting	DESCRIPTION	
Integrity Monitoring	Integrity Monitoring logs events related to file changes system-wide for files, folders, and the registry.	

Enabling or Disabling Feature Settings

Note 🕯

By default, Trend Micro Safe Lock enables all Exploit Prevention settings. If Network Virus Protection was not included in the initial installation, it cannot be selected. Reinstall Trend Micro Safe Lock if Network Virus Protection is not available.

Procedure

- Open the Trend Micro Safe Lock console using the desktop icon (if available) or the Start menu by clicking All Programs > Trend Micro Safe Lock.
- 2. Provide the password and click Login.
- 3. Click the **Settings** menu item to configure Exploit Prevention settings.
- **4.** Enable or disable the desired features.
- 5. Click Save.



Chapter 3

Using the Agent Command Line Interface (CLI)

This chapter describes how to configure and use Trend Micro Safe Lock using the command line interface (CLI).

Topics in this chapter include:

• Using SLCmd at the Command Line Interface (CLI) on page 3-2

Using SLCmd at the Command Line Interface (CLI)

Administrators can work with Trend Micro Safe Lock directly from the command line interface (CLI) using the **SLCmd.exe** program at the command line.

Procedure

- 1. Open a command prompt window with Windows administrator privileges.
- 2. Navigate to the Trend Micro Safe Lock installation folder using the cd command.

For example, type the following command to reach the default location:

cd /d "c:\Program Files\Trend Micro\Trend Micro Safe Lock\"

3. Type SLCmd.exe.

SLCmd Program and Console Function Comparison

The following table lists the Trend Micro Safe Lock features available in SLCmd program and the Safe Lock console program.

TABLE 3-1. SLCmd Program at the Command Line Interface (CLI) and Console Function Comparison

FUNCTION	SLCMD Program at the Command Line Interface (CLI)	Console
Account Management	Yes	Yes
Approved List Management	Yes	Yes
Decrypt/Encrypt configuration file	Yes	No
Display the blocked log	Yes	Yes

FUNCTION	SLCMD Program at the Command Line Interface (CLI)	Console
Export/Import Approved List	Yes	Yes
Export/Import configuration	Yes	Yes
Install	Yes	Yes
Application Lockdown	Yes	Yes
Write Protection	Yes	Yes
Write Protection Exceptions	Yes	No
Integrity Monitoring	Yes	Yes
Exception Paths	Yes	No
License Management	Yes	Yes
Settings	Limited	Limited
Start/Stop Trusted Updater	Yes	Yes
Start/Stop the service	Yes	No
Uninstall	No	No

Not all settings are available through the command line interface (CLI) or console. See *Working with the Agent Configuration File on page 4-2* for information about modifying the system configuration.

SLCmd Program Commands

The following tables list a summary commands available using the **SLCmd** program at the command line interface (CLI). To use the program, type **SLCmd** and the desired command. Type **SLCmd** and press ENTER to display the list of available commands.



Only a Safe Lock administrator with Windows administrator privileges can use **SLCmd** at the command line interface (CLI). **SLCmd** will prompt for the administrator password before running certain commands.

The following is a full list of commands available using the **SLCmd** program.

General Commands

Perform general actions using the Command Line Interface.

The following table lists the available abbreviated forms of parameters.

Parameter	ABBREVI ATION	Use
adminpassword	ap	Manage the Safe Lock admistrator password
lock	10	Manage Application Lockdown status
blockedlog	bl	Manage the applications blocked by Safe Lock
license	lc	Manage the Safe Lock license
settings	set	Manage the Safe Lock settings
service	srv	Manage the Safe Lock service

TABLE 3-2. Abbreviations and Uses

The following table lists the commands, parameters, and values available.

TABLE 3-3. General Commands

COMMAND	PARAMETER	VALUE	DESCRIPTION
help			Display a list of Safe Lock commands
			For example, type:

COMMAND	PARAMETER	VALUE	DESCRIPTION
			SLCmd.exe help
activate		<activatio n_code></activatio 	Activate the Safe Lock program using the specified Activation Code
			For example, type:
			SLCmd.exe activate XX-XXXX- XXXXX-XXXXX-XXXXX-XXXXX
set	adminpassword	<new_pas sword></new_pas 	Change the currently logged on administrator password to the newly specified password
			For example, type:
			SLCmd.exe -p <admin_password> set adminpassword P@ssW0Rd</admin_password>
			Prompt the currently logged on administrator to specify a new password
			For example, type:
			SLCmd.exe -p <admin_password> set adminpassword</admin_password>
set	lock	enable	Turn on Application Lockdown
			For example, type:
			SLCmd.exe -p <admin_password> set lock enable</admin_password>
		disable	Turn off Application Lockdown
			For example, type:
			SLCmd.exe -p <admin_password> set lock disable</admin_password>
			Display the current Safe Lock Application Lockdown status
			For example, type:

COMMAND	PARAMETER	VALUE	DESCRIPTION
			SLCmd.exe -p <admin_password> set lock</admin_password>
show	blockedlog		Display a list of applications blocked by Safe Lock
			For example, type:
			SLCmd.exe -p <admin_password> show blockedlog</admin_password>
show	license		Display the current Safe Lock license information
			For example, type:
			SLCmd.exe show license
show	settings		Display the current status of the vulnerability attack prevention features
			For example, type:
			SLCmd.exe -p <admin_password> show settings</admin_password>
start	service		Start the Safe Lock service
			For example, type:
			SLCmd.exe start service
status			Display the current status of Application Lockdown and the auto update function of the Approved List
			For example, type:
			SLCmd.exe -p <admin_password> status</admin_password>
stop	service		Stop the Safe Lock service
			For example, type:

COMMAND	PARAMETER	VALUE	DESCRIPTION
			SLCmd.exe -p <admin_password> stop service</admin_password>
version			Display the current versions of Safe Lock components
			For example, type:
			SLCmd.exe -p <admin_password> version</admin_password>

Central Management Commands

Configure central management features using the Command Line Interface by typing your command in the following format:

SLCmd.exe -p <admin_password> <command> <parameter> <value>

The following table lists the available abbreviated forms of parameters.

Parameter	Abbrevi Ation	Use
managedmodeconfiguration	mmc	Manage the configuration file
servercertification	sc	Manage server certificate files
managedmode	mm	Manage agent "Managed Mode"

TABLE 3-4. Abbreviations and Uses

TABLE 3-5. Central Management Commands

COMMAND	PARAMETER	VALUE	DESCRIPTION
decrypt	managedmodeconfigur ation	<path_of_ encrypted _file> <path_of_ decrypted</path_of_ </path_of_ 	Decrypt the configuration file used by Managed Mode

COMMAND	PARAMETER	VALUE	DESCRIPTION
		_output_fil e>	
encrypt	managedmodeconfigur ation	<path_of_f ile> <path_of_ encrypted _output_fil e></path_of_ </path_of_f 	Encrypt the configuration file used by Managed Mode
export	managedmodeconfigur ation	<path_of_ encrypted _output></path_of_ 	Export the encrypted configuration file used by Managed Mode
	servercertification	<path_of_ certificatio n_file></path_of_ 	Export the encrypted Safe Lock Intelligent Manager SSL communication certificate file
import	managedmodeconfigur ation	<path_of_ encrypted _input></path_of_ 	Import the encrypted configuration file used by Managed Mode
	servercertification	<path_of_ certificatio n_file></path_of_ 	Import the encrypted Safe Lock Intelligent Manager SSL communication certificate file
set	managedmode	enable [- cfg <path_of_ encrypted _file>] [-sc <path_of_ certificatio n_file>]</path_of_ </path_of_ 	Enable Managed Mode Note Using the optional -cfg value specifies the path of the configuration file. Using the optional -sc value specifies the path of the certificate file.
set	managedmode		Display the current Managed Mode status
show	managedmodeconfigur ation		Display the configuration used by Managed Mode

COMMAND	PARAMETER	VALUE	DESCRIPTION
test	managedmode		Connect a test Managed Mode session with Safe Lock Intelligent Manager

Optional Feature Commands

Configure optional security features using the Command Line Interface by typing your command in the following format:

SLCmd.exe -p <admin_password> <command> <parameter> <value>

The following table lists the available abbreviated forms of parameters.

TABLE 3-6.	Abbreviations	and Uses
------------	---------------	----------

Parameter		Use
usbmalwareprotection	usb	Manage USB Malware Protection
networkvirusprotection	net	Manage Network Virus Protection
memoryrandomization	mr	Manage Memory Randomization
dllinjectionprevention	dll	Manage DLL Injection Prevention
apihookingprevention	api	Manage API Hooking Prevention
dlldriverlockdown	dd	Manage DLL/Driver Lockdown
script	scr	Manage Script Lockdown
writeprotection	wp	Manage Write Protection
writeprotection-includes- approvedlist	wpal	Manage Write Protection includes Approved List
integritymonitoring	in	Manage Integrity Monitoring
customaction	са	Manage actions taken when Safe Lock blocks specific types of events

Parameter	Abbrevi Ation	Use
exceptionpath	ep	Manage exceptions to Application Lockdown

TABLE 3-7. Optional Feature Commands

COMMAND	PARAMETER	VALUE	DESCRIPTION
set	usbmalwareprotectio	enable	Enable USB Malware Protection
	n		For example, type:
			SLCmd.exe -p <admin_password> set usbmalwareprotection enable</admin_password>
		disable	Disable USB Malware Protection
			For example, type:
			SLCmd.exe -p <admin_password> set usbmalwareprotection disable</admin_password>
			Display the current status of USB Malware Protection
			For example, type:
			SLCmd.exe -p <admin_password> set usbmalwareprotection</admin_password>
set	networkvirusprotect	enable	Enable Network Virus Protection
	ion		For example, type:
			SLCmd.exe -p <admin_password> set networkvirusprotection enable</admin_password>
		disable	Disable Network Virus Protection
			For example, type:

COMMAND	PARAMETER	VALUE	DESCRIPTION
			SLCmd.exe -p <admin_password> set networkvirusprotection disable</admin_password>
			Display the current status of Network Virus Protection
			For example, type:
			SLCmd.exe -p <admin_password> set networkvirusprotection</admin_password>
set	memoryrandomization	enable	Enable Memory Randomization
			For example, type:
			SLCmd.exe -p <admin_password> set memoryrandomization enable</admin_password>
		disable	Disable Memory Randomization
			For example, type:
			SLCmd.exe -p <admin_password> set memoryrandomization disable</admin_password>
			Display the current status of Memory Randomization
			For example, type:
			SLCmd.exe -p <admin_password> set memoryrandomization</admin_password>
set	dllinjectionprevent	enable	Enable DLL Injection Prevention
	ion		For example, type:
			SLCmd.exe -p <admin_password> set dllinjectionprevention enable</admin_password>
		disable	Disable DLL Injection Prevention
			For example, type:

COMMAND	PARAMETER	VALUE	DESCRIPTION
			SLCmd.exe -p <admin_password> set dllinjectionprevention disable</admin_password>
			Display the current status of DLL Injection Prevention
			For example, type:
			SLCmd.exe -p <admin_password> set dllinjectionprevention</admin_password>
set	apihookingpreventio	enable	Enable API Hooking Prevention
	n		For example, type:
			SLCmd.exe -p <admin_password> set apihookingprevention enable</admin_password>
		disable	Disable API Hooking Prevention
			For example, type:
			SLCmd.exe -p <admin_password> set apihookingprevention disable</admin_password>
			Display the current status of API Hooking Prevention
			For example, type:
			SLCmd.exe -p <admin_password> set apihookingprevention</admin_password>
set	dlldriverlockdown	enable	Enable DLL/Driver Lockdown
			For example, type:
			SLCmd.exe -p <admin_password> set dlldriverlockdown enable</admin_password>
		disable	Disable DLL/Driver Lockdown
			For example, type:

COMMAND	PARAMETER	VALUE	DESCRIPTION
			SLCmd.exe -p <admin_password> set dlldriverlockdown disable</admin_password>
			Display the current status of DLL/ Driver Lockdown
			For example, type:
			SLCmd.exe -p <admin_password> set dlldriverlockdown</admin_password>
set	script	enable	Enable Script Lockdown
			For example, type:
			SLCmd.exe -p <admin_password> set script enable</admin_password>
		disable	Disable Script Lockdown
			For example, type:
			SLCmd.exe -p <admin_password> set script disable</admin_password>
			Display the current status of Script Lockdown
			For example, type:
			SLCmd.exe -p <admin_password> set script</admin_password>
set	writeprotection	enable	Enable Write Protection
			For example, type:
			SLCmd.exe -p <admin_password> set writeprotection enable</admin_password>
		disable	Disable Write Protection
			For example, type:
			SLCmd.exe -p <admin_password> set writeprotection disable</admin_password>

COMMAND	PARAMETER	VALUE	DESCRIPTION
			Display the current status of Write Protection
			For example, type:
			SLCmd.exe -p <admin_password> set writeprotection</admin_password>
set	writeprotection- includes- approvedlist	enable	Enable protection of the Approved List (in addition to the Write Protection List) when Write Protection is enabled
			For example, type:
			SLCmd.exe -p <admin_password> set writeprotection-includes- approvedlist enable</admin_password>
		disable	Disable protection of the Approved List (in addition to the Write Protection List) when Write Protection is enabled
			For example, type:
			SLCmd.exe -p <admin_password> set writeprotection-includes- approvedlist disable</admin_password>
			Display the current status of Write Protection includes Approved List
			For example, type:
			SLCmd.exe -p <admin_password> set writeprotection-includes- approvedlist</admin_password>
set	integritymonitoring	enable	Enable Integrity Monitoring
			For example, type:
			SLCmd.exe -p <admin_password> set integritymonitoring enable</admin_password>

COMMAND	PARAMETER	VALUE	DESCRIPTION
		disable	Disable Integrity Monitoring
			For example, type:
			SLCmd.exe -p <admin_password> set integritymonitoring disable</admin_password>
			Display the current status of Integrity Monitoring
			For example, type:
			SLCmd.exe -p <admin_password> set integritymonitoring</admin_password>
set	customaction	ignore	Ignore blocked files or processes when Application Lockdown blocks any of the following events:
			Process launch
			DLL loading
			Script file access
		quaranti ne	Quarantine blocked files or processes when Application Lockdown blocks any of the following events:
			Process launch
			DLL loading
			Script file access
			Note Safe Lock does not support a custom action of "quarantine" on Windows XP or Windows 2003.

COMMAND	PARAMETER	VALUE	DESCRIPTION
		ask	Ask what to do for blocked files or processes when Application Lockdown blocks any of the following events:
			Process launch
			DLL loading
			Script file access
			Display the current setting for actions taken when Safe Lock blocks specific types of events
set	exceptionpath	enable	Enable exceptions to Application Lockdown
		disable	Disable exceptions to Application Lockdown
			Display current setting for using exceptions to Application Lockdown

Restricted User Account Commands

Configure the Restricted User Account using the Command Line Interface by typing your command in the following format:

```
SLCmd.exe -p <admin_password> <command> <parameter> <value>
```

The following table lists the available abbreviated forms of parameters.

TABLE 3-8. Abbreviations and Uses

Parameter	Abbrevi Ation	Use
user	us	Manage the Restricted User account
userpassword	up	Manage the Restricted User password

COMMAND	PARAMETER	VALUE	DESCRIPTION
set	user	enable	Enable the Restricted User account
			For example, type:
			SLCmd.exe -p <admin_password> set user enable</admin_password>
		disable	Disable the Restricted User account
			For example, type:
			SLCmd.exe -p <admin_password> set user disable</admin_password>
			Display the the Restricted User account status
			For example, type:
			SLCmd.exe -p <admin_password> set user</admin_password>
set	userpassword	<new_pas sword></new_pas 	Change the Restricted User account password to the newly specified password
			For example, type:
			SLCmd.exe -p <admin_password> set userpassword P@ssW0Rd</admin_password>
			Prompt the currently logged on administrator to specify a new Restricted User account password
			For example, type:
			SLCmd.exe -p <admin_password> set userpassword</admin_password>

TABLE 3-9. Restricted User Account Commands

3-17

Script Commands

Deploy scripts using the Command Line Interface by typing your command in the following format:

SLCmd.exe -p <admin_password> <command> <parameter> <value>

The following table lists the available abbreviated forms of parameters.

TABLE 3-10. Abbreviations and Uses

Parameter		Use
script	scr	Manage script commands

TABLE 3-11. Script Commands

COMMAND	PARAMETER	VALUE	DESCRIPTION
add	script	<extensio n> <interpret er1> [interprete r2]</interpret </extensio 	Add the specified script extension and the interpreter(s) required to execute the script For example, to add the script extension JSP with the interpreter file jscript.js, type: SLCmd.exe -p <admin_password> add script jsp C:\Scripts \jscript.js</admin_password>
remove	script	<extensio n> [interprete r1] [interprete r2]</extensio 	Remove the specified script extension and the interpreter(s) required to execute the script For example, to remove the script extension JSP with the interpreter file jscript.js, type: SLCmd.exe -p <admin_password> remove script jsp C:\Scripts \jscript.js</admin_password>

COMMAND	PARAMETER	VALUE	DESCRIPTION
			Note If you do not specify any interpreter, the command removes all interpreters related to the script extension. If you specify interpreters, the command only removes the interpreters specified from the script extension rule.
show	script		Display all script rules For example, type: SLCmd.exe -p <admin_password> show script</admin_password>

Approved List Commands

Configure the Approved List using the Command Line Interface by typing your command in the following format:

SLCmd.exe -p <admin_password> <command> <parameter> <value>

The following table lists the available abbreviated forms of parameters.

TABLE 3-12. Abbreviations and Uses

Parameter		Use
approvedlist	al	Manage files in the Approved List
list	li	Manage the Approved List import and export functions

COMMAND	PARAMETER	VALUE	DESCRIPTION
add	approvedlist	[-r] <file_or_fo< th=""><th>Add the specified file to the Approved List</th></file_or_fo<>	Add the specified file to the Approved List
		Ider_path>	For example, to add all Microsoft Office files to the Approved List, type:
			SLCmd.exe -p <admin_password> add approvedlist -r "C: \Program Files\Microsoft Office"</admin_password>
			Note Using the optional -r value includes the specified folder and related subfolders.
remove	approvedlist	<file_path ></file_path 	Remove the specified file from the Approved List
			For example, to remove notepad.exe from the Approved List, type:
			SLCmd.exe -p <admin_password> remove approvedlist C:\Windows \notepad.exe</admin_password>
show	approvedlist		Display the files in the Approved List
			For example, type:
			SLCmd.exe -p <admin_password> show approvedlist</admin_password>
check	approvedlist	-f	Update the hash values in the Approved List and displays detailed results
			For example, type:

TABLE 3-13. Approved List Commands

COMMAND	PARAMETER	VALUE	DESCRIPTION
			SLCmd.exe -p <admin_password> check approvedlist -f</admin_password>
		-d	Update the hash values in the Approved List and displays summarized results
			For example, type:
			SLCmd.exe -p <admin_password> check approvedlist -q</admin_password>
		-v	Compare the hash values in the Approved List with the hash values calculated from the actual files and prompts the user after detecting mismatched values
			For example, type:
			SLCmd.exe -p <admin_password> check approvedlist -v</admin_password>
export	list	<output_fil e></output_fil 	Export the Approved List to the file path and file name specified
			For example, type:
			SLCmd.exe -p <admin_password> export list c:\approvedlist \ap.db</admin_password>
			Note The output file type must be DB format.
import	list	[-∘] <input_file< th=""><th>Import an Approved List from the file path and file name specified</th></input_file<>	Import an Approved List from the file path and file name specified
		>	For example, type:
			SLCmd.exe -p <admin_password> import list c:\approvedlist \ap.db</admin_password>

COMMAND	Parameter	VALUE	DESCRIPTION
			Note The input file type must be DB format. Using the optional -○ value overwrites the existing list.

Application Lockdown Commands

Perform actions related to Application Lockdown using the Command Line Interface by typing your command in the following format:

SLCmd.exe -p <admin_password> <command> <parameter> <value>

The following table lists the available abbreviated forms of parameters.

TABLE 3-14. Abbreviations and Uses

Parameter		Use
quarantinedfile	qf	Manage quarantined files
exceptionpath	ep	Manage exceptions to Application Lockdown

TABLE 3-15. Application Lockdown Commands

COMMAND	PARAMETER	VALUE	DESCRIPTION
show	quarantinedfile		Display a list of quarantined files
restore	quarantinedfile	<id>[-al]</id>	Restore the specified file from quarantine
			Using the optional -al value also adds the restored file to Approved List.

COMMAND	PARAMETER	VALUE	DESCRIPTION
			Using the optional -f value forces the restore.
remove	quarantinedfile	<id></id>	Delete the specified file
show	exceptionpath		Display current exceptions to Application Lockdown
add	exceptionpath	-e <file_path >-t file</file_path 	Add an exception for the specified file
		-e <folder_pa th>-t folder</folder_pa 	Add an exception for the specified folder
		-e <folder_pa th>-t folderan dsub</folder_pa 	Add an exception for the specified folder and related subfolders
remove	exceptionpath	-e <file_path >-t file</file_path 	Remove an exception for the specified file
			Note Specify the exact <file_path> originally specified in the corresponding add command.</file_path>
	-e <folder_pa th>-t</folder_pa 	Remove an exception for the specified folder	
	folder	Note Specify the exact <folder_path> originally specified in the corresponding add command.</folder_path>	

COMMAND	PARAMETER	VALUE	DESCRIPTION
		-e <folder_pa th>-t</folder_pa 	Remove an exception for the specified folder and related subfolders
		folderan	
		dsub	Note
			Specify the exact <folder_path> originally specified in the corresponding add command.</folder_path>

Write Protection Commands

Configure Write Protection List and Write Protection Exception List using the Command Line Interface by typing your command in the following format:

SLCmd.exe -p <admin_password> <command> <parameter> <value>

The following table lists the available abbreviated forms of parameters.

TABLE 3-16. Abbreviations and Uses

Parameter	Abbrevi Ation	Use
writeprotection	wp	Manage the Write Protection feature
writeprotection-file	wpfi	Manage files in the Write Protection List
writeprotection-folder	wpfo	Manage folders in the Write Protection List
writeprotection-regvalue	wprv	Manage registry values and associated registry keys in the Write Protection List
writeprotection-regkey	wprk	Manage registry keys in the Write Protection List
writeprotection-file- exception	wpfie	Manage files in the Write Protection Exception List

Parameter	Abbrevi Ation	Use
writeprotection-folder- exception	wpfoe	Manage folders in the Write Protection Exception List
writeprotection-regvalue- exception	wprve	Manage registry values and associated registry keys in the Write Protection Exception List
writeprotection-regkey- exception	wprke	Manage registry keys in the Write Protection Exception List

TABLE 3-17. Write Protection List "File" Commands

COMMAND	PARAMETER	VALUE	DESCRIPTION
show	writeprotection		Display the entire Write Protection List
	writeprotection- file		Display the files in the Write Protection List
			For example, type:
			SLCmd.exe -p <admin_password> show writeprotection-file</admin_password>
	writeprotection- file-exception		Display the files in the Write Protection Exception List
			For example, type:
			SLCmd.exe -p <admin_password> show writeprotection-file- exception</admin_password>
	writeprotection- folder		Display the folders in the Write Protection List
			For example, type:
			SLCmd.exe -p <admin_password> show writeprotection-folder</admin_password>

COMMAND	PARAMETER	VALUE	DESCRIPTION
	writeprotection- folder-exception		Display the folders in the Write Protection Exception List
			For example, type:
			SLCmd.exe -p <admin_password> show writeprotection-folder- exception</admin_password>
add	writeprotection- file	<file_path ></file_path 	Add the specified file to the Write Protection List
			For example, type:
			SLCmd.exe -p <admin_password> add writeprotection-file archive.txt</admin_password>
			Note The <file_path> value pattern matches from the end of the path toward the beginning of the path. For example, specifying userfile.txt matches c:\Windows \userfile.txt and c:\Temp \userfile.txt.</file_path>
	writeprotection- file-exception	-t <file_path >-p <process_ path></process_ </file_path 	Add the specified file and a specific process path for that file to the Write Protection Exception List For example, to add write access by a process named notepad.exe to a file named userfile.txt, type: SLCmd.exe -p <admin_password> add writeprotection-file- exception -t userfile.txt -p notepad.exe</admin_password>

COMMAND	PARAMETER	VALUE	DESCRIPTION
			Note The -p and -t values pattern match from the end of the path toward the beginning of the path. For example, specifying userfile.txt matches c:\Windows \userfile.txt and c:\Temp \userfile.txt.
		-t <file_path ></file_path 	Add the specified file to the Write Protection Exception List For example, to add write access by any process to a file named userfile.txt, type:
			add writeprotection-file- exception -t userfile.txt
			<pre>from the end of the path toward the beginning of the path. For example, specifying userfile.txt matches c: \Windows\userfile.txt and c:\Temp\userfile.txt.</pre>
		-p <process_ path></process_ 	Add the specified process path to the Write Protection Exception List For example, to add write access by a process named notepad.exe to any files type:
			SLCmd.exe -p <admin_password> add writeprotection-file- exception -p notepad.exe</admin_password>

COMMAND	PARAMETER	VALUE	DESCRIPTION
			Note The -p value pattern matches from the end of the process path toward the beginning of the path. For example, specifying notepad.exe matches c:\Windows \notepad.exe and c:\Temp \notepad.exe.
	writeprotection- folder	[-r] <folder_pa< td=""><td>Add the specified folder(s) to the Write Protection List</td></folder_pa<>	Add the specified folder(s) to the Write Protection List
		u1-	For example, type:
			SLCmd.exe -p <admin_password> add writeprotection-folder -r userfolder</admin_password>
			Note Using the optional -r value includes the specified folder and related subfolders.
			The <folder_path> value pattern matches from the end of the path toward the beginning of the path. For example, specifying userfile.txt matches c: \Windows\userfolder and c:\Temp\userfolder.</folder_path>
	writeprotection- folder-exception	[-r] -t <folder_pa th> -p <process_< td=""><td>Add the specified folder and processes run from the specified path to the Write Protection Exception List</td></process_<></folder_pa 	Add the specified folder and processes run from the specified path to the Write Protection Exception List
		path>	For example, to add write access by a process named notepad.exe to a
COMMAND	PARAMETER	VALUE	DESCRIPTION
---------	-----------	--	--
			<pre>folder and related subfolders at c: \Windows\System32\Temp, type: SLCmd.exe -p <admin_password> add writeprotection-folder- exception -r -t c:\Windows \System32\Temp -p notepad.exe</admin_password></pre>
			Note Using the optional -r value includes the specified folder and related subfolders. The -p and -t values pattern match from the end of the path toward the beginning of the path. For example, specifying userfile.txt matches c:\Windows \userfile.txt and c:\Temp \userfile.txt.
		[-r] -t <folder_pa th></folder_pa 	Add the specified folder(s) to the Write Protection Exception List For example, to add write access by any process to a folder at userfolder, type: SLCmd.exe -p <admin_password> add writeprotection-folder- exception -r -t userfolder</admin_password>

COMMAND	PARAMETER	VALUE	DESCRIPTION
			Note Using the optional –r value includes the specified folder and related subfolders.
			The -t value pattern matches from the last part of the folder path toward the beginning of the path. For example, specifying userfolder matches c:\Windows \userfolder and c:\Temp \userfolder.
		-p <process_ path></process_ 	Add processes run from the specified paths to the Write Protection Exception List
			For example, to add write access by a process named notepad.exe to any folder, type:
			SLCmd.exe -p <admin_password> add writeprotection-folder- exception -p c:\Windows \notepad.exe</admin_password>
			Note The -p value pattern matches from the end of the process path toward the beginning of the path. For example, specifying notepad.exe matches c:\Windows \notepad.exe and c:\Temp \notepad.exe.
remove	writeprotection- file	<file_path ></file_path 	Remove the specified file from the Write Protection List
			For example, type:

COMMAND	PARAMETER	VALUE	DESCRIPTION
			SLCmd.exe -p <admin_password> remove writeprotection-file archive.txt</admin_password>
			Note Specify the exact <file_path> originally specified in the corresponding add command.</file_path>
	writeprotection- file-exception	-t <file_path > -p <process< td=""><td>Remove the specified file and process path from the Write Protection Exception List</td></process<></file_path 	Remove the specified file and process path from the Write Protection Exception List
		path>	For example, type: SLCmd.exe -p <admin password=""></admin>
			remove writeprotection-file-
			exception -t userfile.txt -p notepad.exe
			Note Specify the exact <file_path> and <process_path> originally specified in the corresponding add command.</process_path></file_path>
		-t <file_path ></file_path 	Remove the specified file from the Write Protection Exception List For example, type:
			SLCmd.exe -p <admin_password> remove writeprotection-file- exception -t userfile.txt</admin_password>

COMMAND	Parameter	VALUE	DESCRIPTION
			Note The -t value pattern matches from the end of the path toward the beginning of the path. For example, specifying userfile.txt matches c: \Windows\userfile.txt and c:\Temp\userfile.txt.
		-p <process_ path></process_ 	Remove the specified process path from the Write Protection Exception List
			For example, type:
			SLCmd.exe -p <admin_password> remove writeprotection-file- exception -p notepad.exe</admin_password>
			Note The -p value pattern matches from the end of the process path toward the beginning of the path. For example, specifying notepad.exe matches c:\Windows \notepad.exe and c:\Temp \notepad.exe.
	writeprotection- folder	[-r] <folder_pa< td=""><td>Remove the specified folder(s) from the Write Protection List</td></folder_pa<>	Remove the specified folder(s) from the Write Protection List
		u1-	For example, type:
			SLCmd.exe -p <admin_password></admin_password>
			remove writeprotection-folder
			-r c:\Windows

COMMAND	PARAMETER	VALUE	DESCRIPTION
			Note Using the optional -r value includes the specified folder and related subfolders. Specify the exact <folder_path> and -r value originally specified in the corresponding add command.</folder_path>
	writeprotection- folder-exception	[-r] -t <folder_pa th> -p <process_ path></process_ </folder_pa 	Remove the specified folder and process path from the Write Protection Exception List For example, type: SLCmd.exe -p <admin_password> remove writeprotection-folder- exception -r -t c:\Windows \System32\Temp -p c:\Windows \notepad.exe Note Using the optional -r value includes the specified folder and related subfolders. Specify the exact <folder_path>, <process_path>, and -r value originally specified in the</process_path></folder_path></admin_password>
		[-r] -t <folder_pa th></folder_pa 	Remove the specified folder(s) from the Write Protection Exception List For example, type: SLCmd.exe -p <admin_password> remove writeprotection-folder- exception -r -t userfolder</admin_password>

COMMAND	PARAMETER	VALUE	DESCRIPTION
			Note Using the optional -r value includes the specified folder and related subfolders. The -t value pattern matches from the last part of the folder path toward the beginning of the path. For example, specifying userfolder matches c:\Windows \userfolder and c:\Temp \userfolder.
		-p <process_ path></process_ 	Remove the specified process path from the Write Protection Exception List For example, type: SLCmd.exe -p <admin_password> remove writeprotection-folder- exception -p c:\Windows \System32</admin_password>
			Note The -p value pattern matches from the end of the process path toward the beginning of the path. For example, specifying notepad.exe matches c:\Windows \notepad.exe and c:\Temp \notepad.exe.

COMMAND	PARAMETER	VALUE	DESCRIPTION
show	writeprotection		Display the entire Write Protection List
	writeprotection- regvalue		Display the registry values in the Write Protection List
	writeprotection- regvalue-exception		Display the registry values in the Write Protection Exception List
	writeprotection- regkey		Display the registry keys in the Write Protection List
	writeprotection- regkey-exception		Display the registry keys in the Write Protection Exception List
add	writeprotection- regvalue	<path_of_ registry_k ey> <registry_ value></registry_ </path_of_ 	Add the specified registry value and its related registry key to the Write Protection List
			For example, to add the registry value of "testvalue" in the "HKEY \test" registry key to the Write Protection List, type:
			SLCmd.exe -p <admin_password> add writeprotection-regvalue HKEY\test testvalue</admin_password>
	writeprotection- regvalue-exception	-t <path_of_ registry_k ey> <registry_ value> -p <process_ path></process_ </registry_ </path_of_ 	Add the specified registry value and its related registry key and a specific process path for that value to the Write Protection Exception List

TABLE 3-18. Write Protection List "Registry" Commands

COMMAND	PARAMETER	VALUE	DESCRIPTION
			Note This command allows write access by the specified process to the specified registry values. The -p value pattern matches from the end of the path toward the beginning of the path.
		-t <path_of_ registry_k ey> <registry_ value></registry_ </path_of_ 	Add the specified registry value and its related registry key to the Write Protection Exception List Note This command allows write access by any process to the specified registry value.
		-p <process_ path></process_ 	Add the specified process to the Write Protection Exception List
			Note This command allows write access by the specified process to any registry values. The -p value pattern matches from the end of the process
			path toward the beginning of the path.
	writeprotection- regkey	[-r] <path_of_ registry_k ey></path_of_ 	Add the specified registry key to the Write Protection List

COMMAND	PARAMETER	VALUE	DESCRIPTION
			Note Using the optional -r value includes the specified registry key and related subkeys.
	writeprotection- regkey-exception	[-r] -t <path_of_ registry_k ey> -p <process< td=""><td>Add the specified registry key and processes run from the specified path to the Write Protection Exception List</td></process<></path_of_ 	Add the specified registry key and processes run from the specified path to the Write Protection Exception List
		path>	Note
			This command allows write access by the specified process to the specified registry keys.
			Using the optional -r value includes the specified registry key and related subkeys.
			The $-p$ value pattern matches from the end of the process path toward the beginning of the path.
		[-r] -t <path_of_ registry_k</path_of_ 	Add the specified registry key to the Write Protection Exception List
		ey>	Note
			This command allows write access by any process to the specified registry keys.
			Using the optional -r value includes the specified registry key and related subkeys.

COMMAND	PARAMETER	VALUE	DESCRIPTION
		^{-p} <process_ path></process_ 	Add processes run from the specified paths to the Write Protection Exception List
			Note This command allows write access by the specified process to any registry keys. The -p value pattern matches from the end of the process path toward the beginning of the path.
remove	writeprotection- regvalue	<path_of_ registry_k ey> <registry_ value></registry_ </path_of_ 	Remove the specified registry value from the Write Protection List
			Note Specify the exact <path_of_registry_key> and <registry_value> originally specified in the corresponding add command.</registry_value></path_of_registry_key>
	writeprotection- regvalue-exception	-t <path_of_ registry_k ey> <registry_ value> -p <process_ path></process_ </registry_ </path_of_ 	Remove the specified registry value and process path from the Write Protection Exception List

COMMAND	PARAMETER	VALUE	DESCRIPTION
			Note Specify the exact <path_of_registry_key>, <registry_value>, and <process_path> originally specified in the corresponding add command. The -p value pattern matches from the end of the path toward the beginning of the path.</process_path></registry_value></path_of_registry_key>
		-t <path_of_ registry_k ey> <registry_ value></registry_ </path_of_ 	Remove the specified registry value from the Write Protection Exception List
		<pre>-p <process_ path=""></process_></pre>	Remove the specified process path from the Write Protection Exception List
			Note The -p value pattern matches from the end of the path toward the beginning of the path.
	writeprotection- regkey	[-r] <path_of_ registry_k ey></path_of_ 	Remove the specified registry key from the Write Protection List

COMMAND	PARAMETER	VALUE	DESCRIPTION
			Note Specify the exact <path_of_registry_key> and - r value originally specified in the corresponding add command. Using the optional -r value includes the specified registry key and related subkeys.</path_of_registry_key>
	writeprotection- regkey-exception	[-r] -t <path_of_ registry_k ey> -p</path_of_ 	Remove the specified registry key and process path from the Write Protection Exception List
		<process_ path></process_ 	Note Specify the exact <path_of_registry_key>, <process_path>, and -r value originally specified in the corresponding add command</process_path></path_of_registry_key>
			Using the optional -r value includes the specified registry key and related subkeys.
			The $-p$ value pattern matches from the end of the path toward the beginning of the path.
		[-r] -t <path_of_ registry_k ey></path_of_ 	Remove the specified registry key from the Write Protection Exception List
			Note Using the optional -r value includes the specified registry key and related subkeys.

COMMAND	PARAMETER	VALUE	DESCRIPTION
		^{-p} <process_ path></process_ 	Remove the specified process path from the Write Protection Exception List
			Note The -p value pattern matches from the end of the path toward the beginning of the path.

Trusted Certification Commands

Configure Trusted Certificates using the Command Line Interface by typing your command in the following format:

SLCmd.exe -p <admin_password> <command> <parameter> <value>

The following table lists the available abbreviated forms of parameters.

TABLE 3-19. Abbreviations and Uses

Parameter	Abbrevi Ation	Use
trustedcertification	tc	Manage Trusted Certifications

TABLE 3-20. Trusted Certificate Commands

COMMAND	Parameter	VALUE	DESCRIPTION
set	<pre>set trustedcertificatio n</pre>	enable	Enable using Trusted Certifications
		disable	Disable using Trusted Certifications
			Display current setting for using Trusted Certifications

COMMAND	PARAMETER	VALUE	DESCRIPTION
show	trustedcertificatio n	[-v]	Display the certificate files in the Trusted Certifications List
			Using the optional $-v$ value displays detailed information.
add	trustedcertificatio n	-c <file_path< th=""><th>Add the specified certificate file to the Trusted Certifications List</th></file_path<>	Add the specified certificate file to the Trusted Certifications List
		> [-1 <label>] [- u]</label>	Using the optional -1 value specifies the unique label for this certificate file.
			Using the optional $-u$ value treats the file signed by this certificate file as a Trusted Updater.
remove	trustedcertificatio n	-1 <label></label>	Remove a certificate file from the Trusted Certifications List by specifying its label

Trusted Updater Commands

Configure Trusted Updaters using the Command Line Interface by typing your command in the following format:

SLCmd.exe -p <admin_password> <command> <parameter> <value>

The following table lists the available abbreviated forms of parameters.

TABLE 3-21. Abbreviations and Uses

Parameter		Use
trustedupdater	tu	Manage the Predefined Trusted Updater tool process

COMMAND	PARAMETER	VALUE	DESCRIPTION
start	trustedupdater	[-r] <path_of_i nstaller></path_of_i 	Start the Trusted Updater and add the installation packages (EXE and MSI file types) in the specified folder to the Approved List
			Note Using the optional -r value includes the specified folder and related subfolders.
			For example, to include all installation packages in the c: \Installers folder and all sub-folders, type:
			SLCmd.exe -p <admin_password> start trustedupdater -r C: \Installers</admin_password>
stop	trustedupdater	[-f]	Stop the Trusted Updater function
			Note Using the optional -f value specifies that the Trusted Updater does not prompt the administrator before committing a file to the Approved List.
			For example, to stop the Trusted Updater and commit all identified installers (indentified before receiving the stop command) to the Approved List after receiving a prompt, type:

TABLE 3-22. Trusted Updater Comm

COMMAND	PARAMETER	VALUE	DESCRIPTION
			SLCmd.exe -p <admin_password> stop trustedupdater -f</admin_password>

Predefined Trusted Updater Commands



Important

The add command for adding files to the Predefined Trusted Updater List follows a different format than the general commands specified in the Predefined Trusted Updater Commands table. For details on adding files to the Predefined Trusted Updater List, see *Predefined Trusted Updater "Add" Command on page 3-47.*

Configure Predefined Trusted Updaters using the Command Line Interface by typing your command in the following format:

SLCmd.exe -p <admin_password> <command> <parameter> <value>

The following table lists the available abbreviated forms of parameters.

TABLE 3-23. Abbreviations and Uses

Parameter		Use
predefinedtrustedupdater	ptu	Manage files in the Predefined Trusted Updater Lists

TABLE 3-24. Predefined Trusted Updater Commands

COMMAND	PARAMETER	VALUE	DESCRIPTION
add	predefinedtrustedup dater	-e <folder_or _file_exce ption></folder_or 	Add the specified file or folder to the Predefined Trusted Updater Exception List

COMMAND	PARAMETER	VALUE	DESCRIPTION
			Important The add command for adding files to the Predefined Trusted Updater List follows a different format than the other commands specified in the this list. For details on adding files to the Predefined Trusted Updater List (not the Predefined Trusted Updater Exception List), see Predefined Trusted Updater "Add" Command on page 3-47.
			For example, to add notepad.exe to the Predefined Trusted Updater Exception List, type: SLCmd.exe -p <admin_password> add predefinedtrustedupdater - e C:\Windows\notepad.exe</admin_password>
decrypt	predefinedtrustedup dater	<path_of_ encrypted _file> <path_of_ decrypted _output_fil e></path_of_ </path_of_ 	Decrypt a file to the specified location For example, to decrypt c: \Notepad.xen to C:\Editors \notepad.exe, type: SLCmd.exe -p <admin_password> decrypt predefinedtrustedupdater C: \Notepad.xen C:\Editors \notepad.exe</admin_password>
encrypt	predefinedtrustedup dater	<path_of_f ile> <path_of_ encrypted</path_of_ </path_of_f 	Encrypt a file to the specified location For example, to encrypt c: \notepad.exe to C: \Editors \Notepad.xen, type:

COMMAND	PARAMETER	VALUE	DESCRIPTION
		_output_fil e>	<pre>SLCmd.exe -p <admin_password> encrypt predefinedtrustedupdater C: \Editors\notepad.exe C: \Notepad.xen</admin_password></pre>
export	predefinedtrustedup dater	<path_of_ encrypted _output></path_of_ 	Export the Predefined Trusted Updater List to the specified encrypted file For example, type: SLCmd.exe -p <admin_password> export predefinedtrustedupdater C: \Lists\ptu_list.xen</admin_password>
import	predefinedtrustedup dater	<path_of_ encrypted _input></path_of_ 	<pre>Import a Predefined Trusted Updater List from the specified encrypted file For example, type: SLCmd.exe -p <admin_password> import predefinedtrustedupdater C: \Lists\ptu_list.xen</admin_password></pre>
remove	predefinedtrustedup dater	-1 <label_na me></label_na 	Remove the specified labeled rule from the Predefined Trusted Updater List For example, to remove the "Notepad" rule, type: SLCmd.exe -p <admin_password> remove predefinedtrustedupdater -1 Notepad</admin_password>
		-e <folder_or _file_exce ption></folder_or 	Remove the specified exception from the Predefined Trusted Updater Exception List For example, to remove the notepad.exe exception, type:

COMMAND	PARAMETER	VALUE	DESCRIPTION
			<pre>SLCmd.exe -p <admin_password> remove predefinedtrustedupdater -e C: \Windows\notepad.exe</admin_password></pre>
set	predefinedtrustedup dater	enable	Enable the Predefined Trusted Updater List
		disable	Disable the Predefined Trusted Updater List
show	predefinedtrustedup dater		Display the files in the Predefined Trusted Updater List
			For example, type:
			SLCmd.exe -p <admin_password> show predefinedtrustedupdater</admin_password>
		-е	Display the files in the Predefined Trusted Updater Exception List
			For example, type:
			SLCmd.exe -p <admin_password> show predefinedtrustedupdater -e</admin_password>

Predefined Trusted Updater "Add" Command

Add processes, files, or folders to the Predefined Trusted Updater List using the Command Line Interface by typing your command in the following format:

SLCmd.exe -p <admin_password> **add** predefinedtrustedupdater -u <folder_or_file> -t <type_of_object> [<optional_values>]

The following table lists the command, parameter, and base value.

COMMAND	PARAMETER	VALUE	DESCRIPTION
add	predefinedtrustedup dater	<folder_or _file</folder_or 	Add a specified file or folder to the Predefined Trusted Updater List
			For example, to add notepad.exe to the Predefined Trusted Updater List, type:
			SLCmd.exe -p <admin_password> add predefinedtrustedupdater C:\Windows\notepad.exe</admin_password>

TABLE 3-25. Predefined Trusted Updater "Add" Command

Append the following additional values at the end of the command:

TABLE 3-26. Predefine	d Trusted Updater "Add	" Additional Values
-----------------------	------------------------	---------------------

VALUE	Req uire d / Opti onal			Example	
-u <folder_or_ file></folder_or_ 	Req uire d	Add the spec Predefined T	cified file or folder to the rusted Updater List	N/A Note This parame requires the the -t <type_of_obj td="" value.<=""><td>ter use of ject></td></type_of_obj>	ter use of ject>
-t <type_of_o bject></type_of_o 	Req uire d	Specify the ty Predefined T located in -u Available obj process	ype of object to add to the rusted Updater List <folder_or_file> ects types are as follows: Indicates only EXE file types</folder_or_file>	SLCmd.exe -p <admin_password> add predefinedtrustedupda ter -u C:\Windows \notepad.exe -t process</admin_password>	

VALUE	Req uire d / Opti onal	DESCRIPTION		Example	
		file	Indicates only MSI and BAT file types		
		folder	Indicates all EXE, MSI, and BAT files in the specified folder		
		folderands ub	Indicates all EXE, MSI, and BAT files in the specified folder and related subfolders		
-p <parent_pr ocess></parent_pr 	Opti onal	Add the full file path to the specified parent process used to invoke the file(s) specified in -u <folder_or_file></folder_or_file>		<pre>SLCmd.exe -p <admin_password> add predefinedtrustedupda ter -u C:\Windows \notepad.exe -t process -p C:\batch files\note.bat</admin_password></pre>	
-1 <label_nam e></label_nam 	Opti onal	Specify a label name for the file(s) specified in $-u$ <folder_or_file></folder_or_file>		SLCmd.exe -p <admin_password> add predefinedtrustedupda</admin_password>	
		When assign	left blank, Safe Lock is an arbitrary label name.	ter -u C:\Windows \notepad.exe -t process -l EDITOR	
-al enable	Opti onal	Compare the hash values in the Approved List with the hash values calculated from the actual files		SLCmd.exe -p <admin_password> add predefinedtrustedupda ter -u C:\Windows</admin_password>	
		Note Inabled by default even when - al is not specified.		\notepad.exe -t process -al enable	

VALUE	Req uire d / Opti onal	DESCRIPTION	Example
-al disable	Opti onal	Do not compare the hash values in the Approved List with the hash values calculated from the actual files	SLCmd.exe -p <admin_password> add predefinedtrustedupda ter -u C:\Windows \notepad.exe -t process -al disable</admin_password>

Configuration File Commands

Perform actions on the configuration file using the Command Line Interface by typing your command in the following format:

SLCmd.exe -p <admin_password> <command> <parameter> <value>

The following table lists the available abbreviated forms of parameters.

TABLE 3-27. Abbreviations and Uses

Parameter	Abbrevi Ation	Use
configuration	con	Manage the configuration file

TABLE 3-28. Configuration File Commands

COMMAND	PARAMETER	VALUE	DESCRIPTION
decrypt	configuration	<pre><path_of_ _file="" encrypted=""> <path_of_ _output_fil="" decrypted="" e=""></path_of_></path_of_></pre>	Decrypts a configuration file to the specified location For example, to decrypt c: \config.xen to C:\config.xml, type:

COMMAND	PARAMETER	VALUE	DESCRIPTION
			SLCmd.exe -p <admin_password> decrypt configuration C: \config.xen C:\config.xml</admin_password>
encrypt	configuration	<path_of_f ile> <path_of_ encrypted _output_fil e></path_of_ </path_of_f 	Encrypts a configuration file to the specified location For example, to encrypt c: \config.xml to C:\config.xen, type:
			SLCmd.exe -p <admin_password> encrypt configuration C: \config.xml C:\config.xen</admin_password>
export	configuration	<pre><path_of_ _output="" encrypted=""></path_of_></pre>	Export the configuration file to the specified location For example, type: SLCmd.exe -p <admin_password> export configuration C: \config.xen</admin_password>
import	configuration	<path_of_ encrypted _input></path_of_ 	Import a configuration file from the specified location For example, type: SLCmd.exe -p <admin_password> import configuration C: \config.xen</admin_password>



Chapter 4

Working with the Agent Configuration File

This chapter describes how to configure Trend Micro Safe Lock using the configuration file.

Topics in this chapter include:

• Working with the Agent Configuration File on page 4-2

Working with the Agent Configuration File

The configuration file allows administrators to create and deploy a single configuration across multiple machines. See *Exporting or Importing a Configuration File on page* 4-2 for more information.

Changing Advanced Settings

Some settings can only be changed though the configuration file using the command line interface (CLI). See *Using SLCmd at the Command Line Interface (CLI) on page 3-2* for more information.

Procedure

- **1.** Export the configuration file.
- **2.** Decrypt the configuration file.
- 3. Edit the configuration file with Windows Notepad or another text editor.

Important Important

Safe Lock only supports configuration files in the UTF-8 file format.

- 4. Encrypt the edited configuration file.
- 5. Import the edited configuration file.

Exporting or Importing a Configuration File

Trend Micro Safe Lock encrypts the configuration file before export. Users must be decrypt the configuration file before modifying the contents.

Procedure

4-2

 Open the Trend Micro Safe Lock console using the desktop icon (if available) or the Start menu by clicking All Programs > Trend Micro Safe Lock.

- 2. Provide the password and click Login.
- 3. Click the Settings menu item to access the Export/Import Configuration section.

To export the configuration file as a database (.xen) file:

- a. Click **Export**, and choose the location to save the file.
- b. Provide a filename, and click Save.

To import the configuration file as a database (.xen) file:

- a. Click **Import**, and locate the database file.
- b. Select the file, and click **Open**.

Trend Micro Safe Lock overwrites the existing configuration settings with the settings in the database file.

Configuration File Syntax

The configuration file uses the XML format to specify parameters used by Safe Lock.

Important

The configuration file only supports UTF-8 encoding.

Refer to the following example of the configuration file:

```
<?xml version="1.0" encoding="UTF-8"?>
<Configurations version="1.00.000"
   xmlns:xsi="http://www.w3.org/2001/
   XMLSchema-instance"
   xsi:noNamespaceSchemaLocation="WKConfig.xsd">
        <Configuration>
        <AccountGroup>
        <AccountGroup>
        <Account
        ID="{24335D7C-1204-43d1-9CBB-332D688C85B6}"
        Enable="no">
        <Password/>
        </Account>
```

```
</AccountGroup>
<UI>
    <SystemTaskTrayIcon Enable="yes"/>
</UI>
<Feature>
    <ApplicationLockDown LockDownMode="2">
        <WhiteList
        RecentHistoryUnapprovedFilesLimit="50"/>
        <ScriptLockdown Enable="yes">
            <Extension ID="bat">
                <Interpreter>cmd.exe</Interpreter>
            </Extension>
            <Extension ID="cmd">
                <Interpreter>cmd.exe</Interpreter>
            </Extension>
            <Extension ID="com">
                <Interpreter>ntvdm.exe</Interpreter>
            </Extension>
            <Extension ID="dll">
                <Interpreter>ntvdm.exe</Interpreter>
            </Extension>
            <Extension ID="drv">
                <Interpreter>ntvdm.exe</Interpreter>
            </Extension>
            <Extension ID="exe">
                <Interpreter>ntvdm.exe</Interpreter>
            </Extension>
            <Extension ID="js">
                <Interpreter>cscript.exe</Interpreter>
                <Interpreter>wscript.exe</Interpreter>
            </Extension>
            <Extension ID="msi">
                <Interpreter>msiexec.exe</Interpreter>
            </Extension>
            <Extension ID="pif">
                <Interpreter>ntvdm.exe</Interpreter>
            </Extension>
            <Extension ID="ps1">
                <Interpreter>powershell.exe
                </Interpreter>
            </Extension>
            <Extension ID="sys">
```

4-4

```
<Interpreter>ntvdm.exe</Interpreter>
        </Extension>
        <Extension ID="vbe">
            <Interpreter>cscript.exe</Interpreter>
            <Interpreter>wscript.exe</Interpreter>
        </Extension>
        <Extension ID="vbs">
            <Interpreter>cscript.exe</Interpreter>
            <Interpreter>wscript.exe</Interpreter>
        </Extension>
    </ScriptLockdown>
    <TrustedUpdater>
        <PredefinedTrustedUpdater Enable="no">
            <RuleSet/>
        </PredefinedTrustedUpdater>
    </TrustedUpdater>
    <DllDriverLockDown Enable="yes"/>
    <ExceptionPath Enable="no">
        <ExceptionPathList/>
    </ExceptionPath>
    <TrustedCertification Enable="yes"/>
    <WriteProtection Enable="yes" ActionMode="1"
    ProtectApprovedList="yes"/>
    <CustomAction ActionMode="0"/>
</ApplicationLockDown>
<UsbMalwareProtection Enable="yes" ActionMode="1"/>
<DllInjectionPrevention Enable="yes"
ActionMode="1"/>
<ApiHookingPrevention Enable="yes" ActionMode="1"/>
<MemoryRandomization Enable="yes"/>
<NetworkVirusProtection Enable="ves"
ActionMode="1"/>
<IntegrityMonitoring Enable="yes"/>
<Log>
    <EventLog Enable="yes">
        <Level>
            <WarningLog Enable="yes" />
            <InformationLog Enable="yes" />
        </Level>
        <BlockedAccessLog Enable="yes"/>
        <ApprovedAccessLog Enable="yes">
            <TrustedUpdaterLog Enable="yes"/>
```

```
<DllDriverLog Enable="yes"/>
                <ExceptionPathLog Enable="yes"/>
                <TrustedCertLog Enable="yes"/>
                <WriteProtectionLog Enable="yes"/>
            </ApprovedAccessLog>
            <SystemEventLog Enable="yes">
                <ExceptionPathLog Enable="yes"/>
                <WriteProtectionLog Enable="yes"/>
            </SystemEventLog>
            <ListLog Enable="yes"/>
            <UsbMalwareProtectionLog Enable="ves"/>
            <ExecutionPreventionLog Enable="yes"/>
            <NetworkVirusProtectionLog Enable="yes"/>
            <IntegrityMonitoringLog>
                <FileCreatedLog Enable="ves"/>
                <FileModifiedLog Enable="yes"/>
                <FileDeletedLog Enable="yes"/>
                <FileRenamedLog Enable="yes"/>
                <RegValueModifiedLog Enable="yes"/>
                <RegValueDeletedLog Enable="yes"/>
                <RegKeyCreatedLog Enable="yes"/>
                <RegKeyDeletedLog Enable="yes"/>
                <RegKeyRenamedLog Enable="yes"/>
            </IntegrityMonitoringLog>
        </EventLog>
        <DebugLog Enable="no"/>
    </Log>
</Feature>
<ManagedMode Enable="yes">
    <Agent>
        <Port/>
        <SslAllowBeast>1</SslAllowBeast>
    </Agent>
    <Server>
        <HostName/>
        <FastPort/>
        <SlowPort/>
        <ApiKey/>
    </Server>
    <Message>
        <Register Trigger="1"/>
        <Unregister Trigger="1"/>
```

4-6

```
<UpdateStatus Trigger="1"/>
                <UploadBlockedEvent Trigger="1"/>
                <CheckFileHash Trigger="1"/>
                <QuickScanFile Trigger="1"/>
            </Message>
            <MessageRandomization TotalGroupNum="1"
            OwnGroupIndex="0"
                TimePeriod="0"/>
            <Proxy Mode="0">
                <HostName/>
                <Port/>
                <UserName/>
                <Password/>
            </Proxy>
        </ManagedMode>
    </Configuration>
    <Permission>
        <AccountRef
        ID="{24335D7C-1204-43d1-9CBB-332D688C85B6}">
            <UIControl ID="DetailSetting" State="no"/>
            <UIControl ID="LockUnlock" State="yes"/>
            <UIControl ID="LaunchUpdater" State="yes"/>
            <UIControl ID="RecentHistoryUnapprovedFiles"</pre>
                 State="yes"/>
            <UIControl ID="ImportExportList" State="yes"/>
            <UIControl ID="ListManagement" State="yes"/>
        </AccountRef>
    </Permission>
</Configurations>
```

Configuration File Parameters

The configuration file contains sections that specify parameters used by Safe Lock.

TABLE 4-1. Configuration File Sections and Descriptions

SECTION	DESCRIPTION	Additional Information
Configuration	Container for the Configuration section	

SECTION	DESCRIPTION	Additional Information
AccountGroup	Parameters to configure the Restricted User account	See AccountGroup Section on page 4-9. See Account Types on page 2-15.
UI	Parameters to configure the display of the system tray icon	See UI Section on page 4-10.
Feature	Container for the Feature section	
ApplicationLockE UsbMalwareProtect n DllInjectionPrevention ApiHookingPrevention NetworkVirusProtection	own Parameters to configure Safe Lock features and functions ent Image: Control of the sect sect sect sect sect sect sect sec	See Feature Section on page 4-10. See About Feature Settings on page 2-17.
IntegrityMonitor Log	Parameters to configure individual log types	See Log Section on page 4-20.
ManagedMode	Parameters to	Descriptions on page 7-4.
	configure Centralized Management functions	Section on page 4-24.
Permission	Container for the Permission section	

SECTION		Additional Information
AccountRef	Parameters to configure the Safe Lock console controls available to the Restricted User account	See AccountRef Section on page 4-27. See Account Types on page 2-15.

AccountGroup Section

Parameters to configure the Restricted User account

See Account Types on page 2-15.

TABLE 4-2.	Configuration	File AccountGroup	Section	Parameters
------------	---------------	-------------------	---------	------------

	P	ARAMETER	Setting	VALUE			
Со	nfi	guration			Container for the Configuration section		
	Ac	countGroup			Container for the AccountGroup section		
		Account	ID	<guid></guid>	Restricted User account GUID		
			Enable	yes	Enable the Restricted User account		
				no	Disable the Restricted User account		
			Password	<safe_lock _password></safe_lock 	Password for the Restricted User account to access the Safe Lock console		

ΡΑ	RAMETER	Setting	VALUE		
				Note The Safe Lock administrator and Restricted User passwords cannot be the same.	

UI Section

Parameters to configure the display of the system tray icon

	P	ARAMETER	Setting	VALUE			
Cc	nfi	guration			Container for the Configuration section		
	UI				Container for the UI section		
		SystemTask TrayIcon	Enable	yes	Display the system tray icon and Windows notifications		
			no		Hide the system tray icon and Windows notifications		

Feature Section

Parameters to configure Safe Lock features and functions

See About Feature Settings on page 2-17.

TABLE 4-4. Configuration File Feature Section Parameters

Parameter	Setting	VALUE	DESCRIPTION
Configuration			Container for the Configuration section

		PA	RAMETER	Setting	VALUE	DESCRIPTION		
Fe	atu	re				Container for the Feature section		
	Apj	plicationLockDown		plicationLockDown		LockDown Mode	1	Turn on Application Lockdown
					2	Turn off Application Lockdown		
-	WhiteList		RecentHi storyUna pprovedF ilesLimi t	0 - 65535	Maximum number of entries in the Blocked Files log			
		Scri	ptLockDown	Enable	yes	Enable Script Lockdown		
					no	Disable Script Lockdown		
	Extension		ID	<file_exte nsion></file_exte 	File extension for Script Lockdown to block			
						For example, specify a value of MSI to block .msi files.		
	Interpreter		Interpreter		<file_nam e></file_nam 	Interpreter for the specified file extension		
						For example, specify msiexec.exe as the interpreter for .msi files.		
		TrustedUpdater				Container for the TrustedUpdater section		
	PredefinedTrustedU		Enable	yes	Enable Trusted Updater			
		po	later		no	Disable Trusted Updater		
			RuleSet			Container for RuleSet conditions		

Parameter					ER	SETTING	VALUE	DESCRIPTION
				Co	ondition	ID	<unique_ ruleset_n ame></unique_ 	Unique name for the set of rules
					ApprovedLi stCheck	Enable	yes	Enable hash checks for Trusted Updaters
							no	Disable hash checks for Trusted Updaters
					ParentProc ess	Path	<process _path></process 	Path of the parent process to add to the Trusted Updater List
				ΕΣ	ception	Path	<process _path></process 	Path to exclude from the Trusted Updater List
				Rı	ıle	Label	<unique_ rule_nam e></unique_ 	Unique name for this rule
					Updater	Туре	process	Use the specified EXE file
							file	Use the specified MSI or BAT file
							folder	Use the EXE, MSI OF BAT files in the specified folder
							folderan dsub	Use the EXE, MSI OF BAT files in the specified folder and its subfolders
						Path	<updater _path></updater 	Updater path
						Conditio nRef	<conditio n_ID></conditio 	Condition ID to provide a more detailed rule for the updater
	DI	LD	riv	/er	Lockdown	Enable	yes	Enable DLL/Driver Lockdown
		Ρ	ARAMETER	Setting	VALUE	DESCRIPTION		
--	--	---------------	------------------------------------	---------------------------------------	--	---		
					no	Disable DLL/Driver Lockdown		
		Exc	eptionPath	Enable	yes	Enable exception paths		
					no	Disable exception paths		
		E	ExceptionPathList			Container for the Exception List		
		ExceptionPath	Path	<exceptio n_path></exceptio 	Exception path			
				Туре	file	Use only the specified file		
					folder	Use the files in the specified folder		
					folderan dsub	Use the files in the specified folder and its subfolders		
		Tru	stedCertification	Enable	yes	Enable using Trusted Certifications		
					no	Disable using Trusted Certifications		
		E	PredefinedTrustedC ertification	Туре	updater	File signed by this certificate is treated as a Trusted Updater		
					lockdown	File signed by this certificate is not treated as a Trusted Updater		
				Hash	<sha-1_ hash_val ue></sha-1_ 	SHA1-hash value of this certificate		
				Label	<label></label>	Description of this certificate		
				Subject	<subject></subject>	Subject of this certificate		

		PA	RAMETER	SETTING	VALUE	DESCRIPTION
				Issuer	<issuer></issuer>	Issuer of this certificate
	WriteProtection		eProtection	Enable	yes	Enable Write Protection
					no	Disable Write Protection
				ActionMo de	0	Allow actions such as edit, rename, and delete
					1	Block actions such as edit, rename, and delete
				ProtectA pprovedL ist	yes	Enable protection of the Approved List (in addition to the Write Protection List) when Write Protection is enabled
					no	Disable protection of the Approved List (in addition to the Write Protection List) when Write Protection is enabled
		List				Container for the Write Protection List
			File	Path	<file_path ></file_path 	File path
			Folder	Path	<folder_p ath></folder_p 	Folder path
				IncludeS ubfolder	yes	Use the files in the specified folder and its subfolders
					no	Use the files in the specified folder
			RegistryKey	Кеу	<reg_key ></reg_key 	Registry key <reg key=""> can be</reg>
						abbreviated or expanded as shown below:

				RAMETER	Setting	VALUE	DESCRIPTION
							HKEY_LOCAL_MACHI NE\test
							HKLM\test
							HKEY_CURRENT_CO NFIG\test
							HKCC\test
							HKEY_CLASSES_RO OT\test
							HKCR\test
							HKEY_CURRENT_US ER\test
							HKCU\test
							HKEY_USERS\test
							HKU\test
					IncludeS	yes	Include any subkeys
					ubkey	no	Do not include any subkeys
				RegistryValue	Кеу	<reg_key< td=""><td>Registry key</td></reg_key<>	Registry key
						>	<reg_key> can be abbreviated or expanded as shown below:</reg_key>
							HKEY_LOCAL_MACHI NE\test
							HKLM\test
							HKEY_CURRENT_CO NFIG\test
							HKCC\test
							HKEY_CLASSES_RO OT\test
							HKCR\test

		ΡΑ	RAMETER	SETTING	VALUE	DESCRIPTION
						HKEY_CURRENT_US ER\test
						HKCU\test
						HKEY_USERS\test
						HKU\test
				Name	<reg_val ue_name ></reg_val 	Registry value name
		ExceptionList				Container for the Write Protection Exception List
			Process	Path	<process _path></process 	Path of the process
			File	Path	<file_path ></file_path 	File path
			Folder	Path	<folder_p ath></folder_p 	Folder path
				IncludeS ubfolder	yes	Use the files in the specified folder and its subfolders
					no	Use the files in the specified folder
			RegistryKey	Кеу	<reg_key< td=""><td>Registry key</td></reg_key<>	Registry key
					>	<reg_key> can be abbreviated or expanded as shown below:</reg_key>
						HKEY_LOCAL_MACHI NE\test
						HKLM\test
						HKEY_CURRENT_CO NFIG\test
						HKCC\test

PARAMETER					SETTING	VALUE	DESCRIPTION
							HKEY_CLASSES_RO OT\test
							HKCR\test
							HKEY_CURRENT_US ER\test
							HKCU\test
							HKEY_USERS\test
							HKU\test
					IncludeS	yes	Include any subkeys
					иркеу	no	Do not include any subkeys
				RegistryValue	Кеу	<reg_key< td=""><td>Registry key</td></reg_key<>	Registry key
						>	<reg_key> can be abbreviated or expanded as shown below:</reg_key>
							HKEY_LOCAL_MACHI NE\test
							HKLM\test
							HKEY_CURRENT_CO NFIG\test
							HKCC\test
							HKEY_CLASSES_RO OT\test
							HKCR\test
							HKEY_CURRENT_US ER\test
							HKCU\test
							HKEY_USERS\test
							HKU\test

	Ρ	ARAMETER	SETTING	VALUE	DESCRIPTION
			Name	<reg_val ue_name ></reg_val 	Registry value name
Custom		tomAction	ActionMo de	0	Ignore blocked files or processes when Application Lockdown blocks any of the following events:
					Process launch
					DLL loading
					Script file access
				1	Quarantine blocked files or processes when Application Lockdown blocks any of the following events:
					Process launch
					DLL loading
					Script file access
				2	Ask what to do for blocked files or processes when Application Lockdown blocks any of the following events:
					Process launch
					DLL loading
					Script file access
Us	sbMal	wareProtection	Enable	yes	Enable USB Malware Protection
				no	Disable USB Malware Protection
			ActionMo de	0	Allow action by detected malware

PARAMETER	Setting	VALUE	DESCRIPTION
		1	Block action by detected malware
DllInjectionPrevention	Enable	yes	Enable DLL Injection Prevention
		no	Disable DLL Injection Prevention
	ActionMo	0	Allows DLL injections
	de	1	Blocks DLL injections
ApiHookingPrevention	Enable	yes	Enable API Hooking Prevention
		no	Disable API Hooking Prevention
	ActionMo	0	Allow API hooking
	de	1	Block API hooking
MemoryRandomization	Enable	yes	Enable Memory Randomization
		no	Disable Memory Randomization
NetworkVirusProtection	Enable	yes	Enable Network Virus Protection
		no	Disable Network Virus Protection
	ActionMo de	0	Allow action by detected network viruses
		1	Block action by detected network viruses
IntegrityMonitoring	Enable	yes	Enable Integrity Monitoring
		no	Disable Integrity Monitoring

PARAMETER	Setting	VALUE	DESCRIPTION
Log			Container for configuring logs
			See Log Section on page 4-20.

Log Section

Parameters to configure individual log types

See Agent Event Log Descriptions on page 7-4.

TABLE 4-5. Configuration File Log Section Parameters

PARAMETER					ETER	Setting	VALUE	DESCRIPTION
Cc	Configuration						Container for the Configuration section	
	Feature							Container for the Feature section
		Log						Container for configuring logs
		EventLog		Enable	yes	Log the Safe Lock events specified in the following elements		
							no	Do not log the Safe Lock events specified in the following elements
				Le	vel			Container for configuring log levels
					WarningLo g	Enable	yes	Log "Warning" level events related to Safe Lock
							no	Do not log "Warning" level events related to Safe Lock

Par	AME	TER	Setting	VALUE	DESCRIPTION
		Informati onLog	Enable	yes	Log "Information" level events related to Safe Lock
				no	Do not log "Information" level events related to Safe Lock
	Bl	ockedAcces	Enable	yes	Log files blocked by Safe Lock
	sl	og		no	Do not log files blocked by Safe Lock
		provedAcce Log	Enable	yes	Log files approved by Safe Lock
				no	Do not log files approved by Safe Lock
		TrustedUp daterLog	Enable	yes	Log Trusted Updater approved access
				no	Do not log Trusted Updater approved access
		DLLDriver Log	Enable	yes	Log DLL/Driver approved access
				no	Do not log DLL/Driver approved access
		Exception PathLog	Enable	yes	Log Application Lockdown exception path approved access
				no	Do not log Application Lockdown exception path approved access
		TrustedCe rtLog	Enable	yes	Log Trusted Certifications approved access
				no	Do not log Trusted Certifications approved access

Par	AME	ETER	Setting	VALUE	DESCRIPTION
		WriteProt ectionLog	Enable	yes	Log Write Protection approved access
				no	Do not log Write Protection approved access
	Sy og	vstemEventL	Enable	yes	Log events related to the system
				no	Do not log events related to the system
		Exception PathLog	Enable	yes	Log exceptions to Application Lockdown
				no	Do not log exceptions to Application Lockdown
		WriteProt	Enable	yes	Log Write Protection events
		ectionLog		no	Do not log Write Protection events
	Li	stLog	Enable	yes	Log events related to the Approved list
				no	Do not log events related to the Approved list
	US ot	BMalwarePr ectionLog	Enable	yes	Log events that trigger USB Malware Protection
				no	Do not log events that trigger USB Malware Protection
	Ex ve	ecutionPre ntionLog	Enable	yes	Log events that trigger Execution Prevention
				no	Do not log events that trigger Execution Prevention
	Ne Pr q	etworkVirus cotectionLo	Enable	yes	Log events that trigger Network Virus Protection

ΡΑ	RAME	TER	Setting	VALUE	DESCRIPTION
				no	Do not log events that trigger Network Virus Protection
	In it	tegrityMon oringLog			Container for configuring Integrity Monitoring logs
		FileCreat edLog	Enable	yes	Log file and folder created events
				no	Do not log file and folder created events
		FileModif	Enable	yes	Log file modified events
		iedLog		no	Do not log file modified events
		FileDelet edLog	Enable	yes	Log file and folder deleted events
				no	Do not log file and folder deleted events
		FileRenam edLog	Enable	yes	Log file and folder renamed events
				no	Do not log file and folder renamed events
		RegValueM odifiedLo	Enable	yes	Log registry value modified events
		đ		no	Do not log registry value modified events
		RegValueD eletedLog	Enable	yes	Log registry value deleted events
				no	Do not log registry value deleted events
		RegKeyCre	Enable	yes	Log registry key created events
		atedLog		no	Do not log registry key created events

Parameter				ETER	Setting	VALUE	DESCRIPTION
				RegKeyDel	Enable	yes	Log registry key deleted events
			etedLog			no	Do not log registry key deleted events
				RegKeyRen amedLog	Enable	yes	Log registry key renamed events
						no	Do not log registry key renamed events
		DebugLog		gLog	Enable	yes	Log debugging information
						no	Do not log debugging information

ManagedMode Section

Parameters to configure Centralized Management functions

 TABLE 4-6. Configuration File ManagedMode Section Parameters

PARAMETER			AMETER	Setting	VALUE	
Configuration			ation			Container for the Configuration section
	ManagedMode			Enable	yes	Enable managed mode
					no	Disable managed mode
	Agent		ent			Container for configuring Safe Lock agents
			Port		<server_me ssages_port ></server_me 	Specify the secure port for server communications (formerly the agent listening port)
			SslAllowBe ast		0	Allow upload of large files (>10MB) on Windows Server 2008 platforms

4-24

PAF	AMETER	Setting	VALUE	DESCRIPTION
			1	Prevent the unsuccessful upload of large files (>10MB) on Windows Server 2008 platforms (default value)
Se	rver			Container for configuring Safe Lock Intelligent Manager
	HostName		<hostname ></hostname 	Specify the host name of the Intelligent Manager server
	FastPort		<logs_port></logs_port>	Specify secure port for collecting logs and status (formerly Fast Lane)
	SlowPort		<files_port></files_port>	Specify secure port for collecting files for scanning (formerly Slow Lane)
	АріКеу		<api_key></api_key>	Specify API key
Me	ssage			Container for configuring automated messages to Safe Lock Intelligent Manager
	Register	Trigger	1	Send as soon as possible after the event occurs
			2	Do not send unless requested to by Intelligent Manager
	Unregister	Trigger	1	Send as soon as possible after the event occurs
			2	Do not send unless requested to by Intelligent Manager
	UpdateStat us	Trigger	1	Send as soon as possible after the event occurs
			2	Do not send unless requested to by Intelligent Manager

ΡΑ	RAMETER	Setting	VALUE	DESCRIPTION
	UploadBloc kedEvent	Trigger	1	Send as soon as possible after the event occurs
			2	Do not send unless requested to by Intelligent Manager
	CheckFileH ash	Trigger	1	Send as soon as possible after the event occurs
			2	Do not send unless requested to by Intelligent Manager
	QuickScanF ile	Trigger	1	Send as soon as possible after the event occurs
			2	Do not send unless requested to by Intelligent Manager
Ме і 2	essageRandom zation	TotalGroup Num	Positive Integer (>= 1)	Specify the total number of message time groups
	Note Safe Lock agents respond as soon	OwnGroupIn dex	Zero or Positive Integer, < TotalGroup Num	Specify the message time group ID number of this Safe Lock agent
	as possible to direct requests from Safe Lock Intelligen t Manager.	TimePeriod	Zero or Positive Integer	Specify the duration of time in whole seconds that this message time group ID number will send automated messages to Intelligent Manager when this group's message-sending cycle is active Note Message time groups do not become active if their duration is set to zero (0).

		Par	AMETER	Setting	VALUE	DESCRIPTION
	Proxy		oxy	Mode	0	Do not use a proxy (direct access)
					1	Use a proxy (manual setting)
					2	Synchronize proxy settings with Internet Explorer
			HostName		<proxy_hos tname></proxy_hos 	Specify the proxy host name
			Port		<proxy_port ></proxy_port 	Specify the proxy port number
			UserName		<proxy_use r_name></proxy_use 	Specify the proxy user name
			Password		<proxy_pas sword></proxy_pas 	Specify the proxy password

AccountRef Section

Parameters to configure the Safe Lock console controls available to the Restricted User account

See Account Types on page 2-15.

TABLE 4-7. Configuration File AccountRef Section Parameters

	PARAMETER	Setting	VALUE	DESCRIPTION
Co	nfiguration			Container for the Configuration section
	Permission			Container for the Permission section
	AccountRef			Container for the AccountRef section

PARAMETER			Setting	VALUE	DESCRIPTION
		UIControl	ID	DetailSett ing	Access the features and functions on the Safe Lock console Settings page
					Note The Password page is not available to the Restricted User account.
				LockUnlock	Access the Application Lockdown setting on the Overview screen
				LaunchUpda ter	Access the Automatically add files created or modified by the selected application installer option when a Restricted User clicks Add Item on the Approved List screen
				RecentHist oryUnappro vedFIles	Access the Block logs if a Restricted User clicks Last application blocked on the Overviewscreen
				ImportExpo rtList	Access the Import List and Export List buttons
				ListManage ment	Access the following items on the Approved List screen:
					The Delete Item button
					The Update Hash button
					The Add Item > Add Files/ Folders menu
			State	yes	Enable the permission specified by ID
				no	Disable the permission specified by ID



Chapter 5

Troubleshooting

This chapter describes troubleshooting techniques and frequently asked questions about Trend Micro Safe Lock.

Topics in this chapter include:

- Frequently Asked Questions (FAQ) on page 5-2
- Troubleshooting Safe Lock on page 5-2

Frequently Asked Questions (FAQ)

What if the endpoint becomes infected by a threat?

Use Trend Micro Portable Security to remove the threat without having to update the Approved List or turn off Application Lockdown at the endpoint.

Where can I get more help with Trend Micro Safe Lock?

Get the most up-to-date information and support from the Trend Micro support website at:

http://esupport.trendmicro.com/en-us/business/

Troubleshooting Safe Lock

The Trend Micro Safe Lock Diagnostic Toolkit offers administrators the ability to perform a number of diagnostic functions, including:

- Create, collect, and delete debugging logs
- Enable or disable Self Protection

A] Debug	[B] Uninstall	[C] Others			
Debug Lo	g Setting				
Applicatio	n Debug Log:				
Not	output any log	IS			
Out	put only errors				
Out	put error logs a	and debug information	1		
Driver De	bug Log:				
Out	put driver debu	ug information		ĺ	Apply
Collect D After re generat	ebug Log produce the p te the needdec	roblem, set path of tr d information.	oubleshooting logs and o	click Collect Debug I	Log button to
Trouble	shooting Logs:				
C:\Pro	gram Files\Tre	nd Micro \Trend Micro	Safe Lock\Log\Archive\		Browse
			Collect	Debug Log	Open Folder

FIGURE 5-1. The Trend Micro Safe Lock Diagnostic Toolkit Debug Tab

[A] Debug	[B] Uninstall	[C] Others	
Only clic Otherwi instead.	k this button if se, open the C	you have encountered installation problems. ontrol Panel and use the uninstall feature there	Uninstall Software
			Close

FIGURE 5-2. The Trend Micro Safe Lock Diagnostic Uninstall Tab

Debug [B] Uninstall [C] Others	
Self Protection	
Manually start or stop Self Protection	Stop Self Protection
Delete Log Files	
Remove all saved log and debug files	
	Delete Log Files
Debug Logs	
C:\Program Files\Trend Micro\Trend Micro Safe Lock\Log\	Browse
	Apply

FIGURE 5-3. The Trend Micro Safe Lock Diagnostic Toolkit Others Tab

Using the Diagnostic Toolkit

If Trend Micro Safe Lock experiences problems, generate a complete set of application and driver diagnostic logs for analysis, or send them to to Trend Micro Technical Support. Both the Safe Lock administrator and Restricted User accounts can collect the logs.

Procedure

- 1. Open the Diagnostic Toolkit and enable full logging:
 - a. Open the Trend Micro Safe Lock installation folder and run WKSupportTool.exe.



The default installation location is c:\Program Files\Trend Micro \Safe Lock\.

- b. Provide the Safe Lockadministrator or Restricted User password and click **OK**.
- c. On the **[A] Debug** tab, select **Output error logs and debug information** and **Output driver debug information**, and click **Apply**.
- **2.** Reproduce the problem.
- **3.** Collect the diagnostic logs:
 - a. Reopen the Diagnostic Toolkit.
 - b. On the **[A] Debug** tab, click **Browse** to choose the location where Trend Micro Safe Lock saves the logs.

Mote Note

The default location for saved logs is: c:\Program Files\Trend Micro \Safe Lock\Log\Archive\.

- c. Click **OK** when finished.
- d. Click Collect Debug Log.
- e. Once the Debug Logs have been collected, click **Open Folder** to access the zipped log files for review, or to send them to Trend Micro Technical Support.

Diagnostic Toolkit Commands

The following table lists the commands available using the Diagnostic Toolkit, WKSupportTool.exe.

Note 🖉

Only the Safe Lock administrator can use the Diagnostic Toolkit, and WKSupportTool.exe will prompt for the administrator password before running a command.

TABLE 5-1. Diagnostic Toolkit Commands

Command	DESCRIPTION
-p <password></password>	Authenticates the user, allowing the command to run.
debug [on off] [verbose normal] [-drv on] [-drv off]	Turns the debug logs on or off, specifies the log detail level, and if driver logs are included.
collect [path]	Collects debugging information and creates a zip file to the specified path. If no path is specified, the default log location <installation directory=""> \Log\Archive is used.</installation>
selfprotection [on off]	Turns on or off Safe Lock self protection.
deletelogs	Deletes all Safe Lock logs.
uninstall	Uninstalls Trend Micro Safe Lock.
changelogpath [path]	Change debug log output folder.



Chapter 6

Technical Support

This chapter describes how to find solutions online, use the Support Portal, and contact Trend Micro.

Topics include:

- Troubleshooting Resources on page 6-2
- Contacting Trend Micro on page 6-3
- Other Resources on page 6-4
- About Trend Micro on page 6-5

Troubleshooting Resources

Before contacting technical support, consider visiting the following Trend Micro online resources.

Using the Support Portal

The Trend Micro Support Portal is a 24x7 online resource that contains the most up-todate information about both common and unusual problems.

Procedure

- 1. Go to <u>http://esupport.trendmicro.com</u>.
- **2.** Select a product or service from the appropriate drop-down list and specify any other related information.

The **Technical Support** product page appears.

- 3. Use the Search Support box to search for available solutions.
- 4. If no solution is found, click **Submit a Support Case** from the left navigation and add any relevant details, or submit a support case here:

http://esupport.trendmicro.com/srf/SRFMain.aspx

A Trend Micro support engineer investigates the case and responds in 24 hours or less.

Trend Community

To get help, share experiences, ask questions, and discuss security concerns with other users, enthusiasts, and security experts, go to:

http://community.trendmicro.com/

Contacting Trend Micro

In the United States, Trend Micro representatives are available by phone, fax, or email:

Address	Trend Micro, Inc. 10101 North De Anza Blvd., Cupertino, CA 95014
Phone	Toll free: +1 (800) 228-5651 (sales)
	Voice: +1 (408) 257-1500 (main)
Fax	+1 (408) 257-2003
Website	http://www.trendmicro.com
Email address	support@trendmicro.com

• Worldwide support offices:

http://www.trendmicro.com/us/about-us/contact/index.html

Trend Micro product documentation:

http://docs.trendmicro.com

Related information

→ Speeding Up the Support Call

Speeding Up the Support Call

To improve problem resolution, have the following information available:

- Steps to reproduce the problem
- Appliance or network information
- · Computer brand, model, and any additional hardware connected to the endpoint
- Amount of memory and free hard disk space
- · Operating system and service pack version
- Endpoint agent version

- Serial number or activation code
- Detailed description of install environment
- Exact text of any error message received

Other Resources

In addition to solutions and support, there are many other helpful resources available online to stay up to date, learn about innovations, and be aware of the latest security trends.

Related information

- → TrendEdge
- → Download Center
- → TrendLabs

TrendEdge

Find information about unsupported, innovative techniques, tools, and best practices for Trend Micro products and services. The TrendEdge database contains numerous documents covering a wide range of topics for Trend Micro partners, employees, and other interested parties.

See the latest information added to TrendEdge at:

http://trendedge.trendmicro.com/

Download Center

From time to time, Trend Micro may release a patch for a reported known issue or an upgrade that applies to a specific product or service. To find out whether any patches are available, go to:

http://www.trendmicro.com/download/

If a patch has not been applied (patches are dated), open the Readme file to determine whether it is relevant to your environment. The Readme file also contains installation instructions.

TrendLabs

TrendLabs^{ss} is a global network of research, development, and action centers committed to 24x7 threat surveillance, attack prevention, and timely and seamless solutions delivery. Serving as the backbone of the Trend Micro service infrastructure, TrendLabs is staffed by a team of several hundred engineers and certified support personnel that provide a wide range of product and technical support services.

TrendLabs monitors the worldwide threat landscape to deliver effective security measures designed to detect, preempt, and eliminate attacks. The daily culmination of these efforts is shared with customers through frequent virus pattern file updates and scan engine refinements.

Learn more about TrendLabs at:

http://cloudsecurity.trendmicro.com/us/technology-innovation/experts/ index.html#trendlabs

About Trend Micro

As a global leader in cloud security, Trend Micro develops Internet content security and threat management solutions that make the world safe for businesses and consumers to exchange digital information. With over 20 years of experience, Trend Micro provides top-ranked client, server, and cloud-based solutions that stop threats faster and protect data in physical, virtualized, and cloud environments.

As new threats and vulnerabilities emerge, Trend Micro remains committed to helping customers secure data, ensure compliance, reduce costs, and safeguard business integrity. For more information, visit:

http://www.trendmicro.com

Trend Micro and the Trend Micro t-ball logo are trademarks of Trend Micro Incorporated and are registered in some jurisdictions. All other marks are the trademarks or registered trademarks of their respective companies.



Chapter 7

Appendix: Reference

This Installation Guide introduces Trend Micro Safe Lock and guides administrators through installation and deployment.

Topics in this chapter include:

- Enabling Local Administrator Accounts on page 7-2
- Enabling Local Accounts for Default Shares on page 7-3
- Agent Event Log Descriptions on page 7-4
- Agent Error Code Descriptions on page 7-25

Enabling Local Administrator Accounts

Windows NT Version 6.x (Windows Vista, Windows 7, Windows 8, Windows 8.1, Windows Server 2008 and Windows Server 2012) requires special steps to allow you to use local Windows administrator accounts.

Procedure

- 1. Open Computer Management.
 - a. Open the **Start** menu.
 - b. Right-click Computer.
 - c. Go to Manage.

The Computer Management window appears.

 In the list on the left, go to Computer Management > System Tools > Local Users and Groups > Users.

The list of local Windows user accounts displays.

3. In the list of user accounts, right-click Administrator, then go to Properties.

The Administrator Properties window appears.

- 4. In the General tab, clear Account is disabled.
- 5. Click OK.

The **Computer Management** window reappears, displaying the list of local Windows user accounts.

6. Right-click Administrator, then go to Set Password....

A message displays instructions for setting the password.

- 7. Set the password.
- 8. Exit Computer Management.

Enabling Local Accounts for Default Shares

Windows NT Version 6.x (Windows Vista, Windows 7, Windows 8, Windows 8.1, Windows Server 2008 and Windows Server 2012) requires special steps to allow local Windows administrator accounts to access default shares, for example the default share admin\$.



Steps vary depending on your Windows version. For specific instructions and help for your Windows version, refer to the Microsoft Knowledgebase at http://msdn.microsoft.com.

Procedure

- 1. Open Registry Editor (regedit.exe).
 - a. Go to Start > Run
 - b. Type **regedit**, then press ENTER.
- 2. Locate and click the following registry subkey:

HKEY_LOCAL_MACHINE\SOFTWARE\Microsoft\Windows
\CurrentVersion\Policies\System

3. Locate the LocalAccountTokenFilterPolicy registry entry.

If the registry entry does not exist, follow these steps:

- a. Go to **Edit** > New.
- b. Select DWORD Value.
- c. Type LocalAccountTokenFilterPolicy, then press ENTER.
- Right-click LocalAccountTokenFilterPolicy, then go to Modify.
- 5. In the Valuefield, type 1.
- 6. Click OK.

7. Exit Registry Editor.

Agent Event Log Descriptions

Trend Micro Safe Lock leverages the WindowsTM Event Viewer to display the Safe Lock event log. Access the Event Viewer at **Start > Control Panel > Administrative Tools**.



Tip

Safe Lock event logging can be customized by doing the following:

- Before installation, modify the Setup.ini file. See *Setup.ini File Arguments > EventLog Section* in the Safe Lock Installation Guide.
- After installation, modify the configuration file. See Configuration File Parameters > Log Section on page 4-20.

Event ID	Task Category	LEVEL	DESCRIPTION
1000	System	Information	Service started.
1001	System	Warning	Service stopped.
1002	System	Information	Application Lockdown Turned On.
1003	System	Warning	Application Lockdown Turned Off.
1004	System	Information	Disabled.
1005	System	Information	Administrator password changed.
1006	System	Information	Restricted User password changed.
1007	System	Information	Restricted User account enabled.
1008	System	Information	Restricted User account disabled.
1009	System	Information	Product activated.

Event ID	Task Category	LEVEL	DESCRIPTION
1010	System	Information	Product deactivated.
1011	System	Warning	License Expired. Grace period enabled.
1012	System	Warning	License Expired. Grace period ended.
1013	System	Information	Product configuration import started: <full_path></full_path>
1014	System	Information	Product configuration import complete: <full_path></full_path>
1015	System	Information	Product configuration exported to: <full_path></full_path>
1016	System	Information	USB Malware Protection set to Allow.
1017	System	Information	USB Malware Protection set to Block.
1018	System	Information	USB Malware Protection enabled.
1019	System	Warning	USB Malware Protection disabled.
1020	System	Information	Network Virus Protection set to Allow.
1021	System	Information	Network Virus Protection set to Block.
1022	System	Information	Network Virus Protection enabled.
1023	System	Warning	Network Virus Protection disabled.
1025	System	Information	Memory Randomization enabled.
1026	System	Warning	Memory Randomization disabled.
1027	System	Information	API Hooking Prevention set to Allow.
1028	System	Information	API Hooking Prevention set to Block.
1029	System	Information	API Hooking Prevention enabled.
1030	System	Warning	API Hooking Prevention disabled.
1031	System	Information	DLL Injection Prevention set to Allow.
1032	System	Information	DLL Injection Prevention set to Block.

Event ID	Task Category	Level	DESCRIPTION
1033	System	Information	DLL Injection Prevention enabled.
1034	System	Warning	DLL Injection Prevention disabled.
1035	System	Information	Auto Trusted Update enabled.
1036	System	Information	Auto Trusted Update disabled.
1037	System	Information	DLL/Driver Lockdown enabled.
1038	System	Warning	DLL/Driver Lockdown disabled.
1039	System	Information	Script Lockdown enabled.
1040	System	Warning	Script Lockdown disabled.
1041	System	Information	Script added.
			[Details]
			File extension: <extension></extension>
			Interpreter: <interpreter></interpreter>
1042	System	Information	Script removed.
			[Details]
			File extension: <extension></extension>
			Interpreter: <interpreter></interpreter>
1044	System	Information	Exception path enabled.
1045	System	Information	Exception path disabled.
Event ID	Task Category	LEVEL	DESCRIPTION
-------------	------------------	-------------	---
1046	System	Information	Event Log settings changed.
			[Details]
			Windows Event Log: <on off></on off>
			System Log: <on off></on off>
			Exception Path Log: <on off></on off>
			Write Protection Log: <on off></on off>
			List Log: <on off></on off>
			Approved Access Log: <on off></on off>
			DLL Driver Log: <on off></on off>
			Trusted Updater Log: <on off></on off>
			Exception Path Log: <on off></on off>
			Trusted Certification Log: <on off></on off>
			Write Protection Log: <on off></on off>
			Blocked Access Log: <on off></on off>
			USB Malware Protection Log: <on off></on off>
			Execution Prevention Log: <on off></on off>
			Network Virus Protection Log: <on off></on off>
			Integrity Monitoring Log File Created Log: <on off=""></on >
			File Modified Log: <on off></on off>
			File Deleted Log: <on off></on off>
			File Renamed Log: <on off></on off>
			RegValue Modified Log: <on off></on off>
			RegValue Deleted Log: <on off></on off>
			RegKey Created Log: <on off></on off>
			RegKey Deleted Log: <on off></on off>
			RegKey Renamed Log: <on off></on off>
			Debug Log: <on off> 7-7</on off>

Event ID	Task Category	Level	DESCRIPTION
1047	System	Information	Trusted certificate enabled.
1048	System	Information	Trusted certificate disabled.
1049	System	Information	Write Protection enabled.
1050	System	Warning	Write Protection disabled.
1051	System	Information	Write Protection set to Allow.
1052	System	Information	Write Protection set to Block.
1055	System	Information	Added file to Write Protection List.
			Path: <full_path></full_path>
1056	System	Information	Removed file from Write Protection List.
			Path: <full_path></full_path>
1057	System	Information	Added file to Write Protection Exception List
			Path: <full_path></full_path>
			Process: <process></process>
1058	System	Information	Removed file from Write Protection Exception List.
			Path: <full_path></full_path>
			Process: <process></process>
1059	System	Information	Added folder to Write Protection List.
			Path: <full_path></full_path>
			Scope: Folder
1060	System	Information	Removed folder from Write Protection List.
			Path: <full_path></full_path>
			Scope: Folder

Event ID	Task Category	Level	DESCRIPTION
1061	System	Information	Added folder to Write Protection Exception List.
			Path: <full_path></full_path>
			Scope: Folder
			Process: <process></process>
1062	System	Information	Removed folder from Write Protection Exception List.
			Path: <full_path></full_path>
			Scope: Folder
			Process: <process></process>
1063	System	Information	Added registry value to Write Protection List.
			Registry Key: <reg_key></reg_key>
			Registry Value Name: <reg_value></reg_value>
1064	System	Information	Removed registry value from Write Protection List.
			Registry Key: <reg_key></reg_key>
			Registry Value Name: <reg_value></reg_value>
1065	System	Information	Added registry value to Write Protection Exception List.
			Registry Key: <reg_key></reg_key>
			Registry Value Name: <reg_value></reg_value>
			Process: <process></process>
1066	System	Information	Removed registry value from Write Protection Exception List.
			Registry Key: <reg_key></reg_key>
			Registry Value Name: <reg_value></reg_value>
			Process: <process></process>

Event ID	Task Category	Level	DESCRIPTION
1067	System	Information	Added registry key to Write Protection List.
			Registry Key: <reg_key></reg_key>
			Scope: Registry Key
1068	System	Information	Removed registry key from Write Protection List.
			Registry Key: <reg_key></reg_key>
			Scope: Registry Key
1069	System	Information	Added registry key to Write Protection Exception List.
			Registry Key: <reg_key></reg_key>
			Scope: Registry Key
			Process: <process></process>
1070	System	Information	Removed registry key from Write Protection Exception List.
			Registry Key: <reg_key></reg_key>
			Scope: Registry Key
			Process: <process></process>
1071	System	Information	Custom Action set to Ignore.
1072	System	Information	Custom Action set to Quarantine.
1073	System	Information	Custom Action set to Ask Intelligent Manager.
1074	System	Information	Quarantined file is restored.
			[Details]
			Original Location: <full_path></full_path>
			Source: <source/>

Event ID	Task Category	LEVEL	DESCRIPTION
1075	System	Information	Quarantined file is deleted.
			[Details]
			Original Location: <full_path></full_path>
			Source: <source/>
1076	System	Information	Integrity Monitoring enabled.
1077	System	Information	Integrity Monitoring disabled.
1078	System	Information	Root cause analysis report failed.
			[Details]
			Access Image Path: <full_path></full_path>
1079	System	Information	Server certificate imported: <full_path></full_path>
1080	System	Information	Server certificate exported to: <full_path></full_path>
1081	System	Information	Managed mode configuration imported: <full_path></full_path>
1082	System	Information	Managed mode configuration exported to: <full_path></full_path>
1083	System	Information	Managed mode enabled.
1084	System	Information	Managed mode disabled.
1085	System	Information	When Write Protection is enabled, it includes the Write Protection List and the Approved List.
1086	System	Warning	When Write Protection is enabled, it includes the Write Protection List only.
1500	List	Information	Trusted Update started.
1501	List	Information	Trusted Update stopped.
1502	List	Information	Approved List import started: <full_path></full_path>

Event ID	Task Category	Level	DESCRIPTION
1503	List	Information	Approved List import complete: <full_path></full_path>
1504	List	Information	Approved List exported to: <full_path></full_path>
1505	List	Information	Added to Approved List: <full_path></full_path>
1506	List	Information	Added to Trusted Update List: <full_path></full_path>
1507	List	Information	Removed from Approved List: <full_path></full_path>
1508	List	Information	Removed from Trusted Update List: <full_path></full_path>
1509	List	Information	Approved List updated: <full_path></full_path>
1510	List	Information	Trusted Update List updated: <full_path></full_path>
1511	List	Warning	Unable to add to or update Approved List: <pre><ful_path></ful_path></pre>
1512	List	Warning	Unable to add to or update Trusted Update List: <pre><ful_path></ful_path></pre>
1513	List	Information	Added to Exception Path List.
			[Details]
			Type: <exception_path_type></exception_path_type>
			Path: <exception_path></exception_path>
1514	List	Information	Removed from Exception Path List.
			[Details]
			Type: <exception_path_type></exception_path_type>
			Path: <exception_path></exception_path>

Event ID	Task Category	LEVEL	DESCRIPTION
1515	List	Information	Added to Trusted Certificate List.
			[Details]
			Label: <label></label>
			Hash: <hash_value></hash_value>
			Type: <type></type>
			Subject: <subject></subject>
			Issuer: <issuer></issuer>
1516	List	Information	Removed from Trusted Certificate List.
			[Details]
			Label: <label></label>
			Hash: <hash_value></hash_value>
			Type: <type></type>
			Subject: <subject></subject>
			Issuer: <issuer></issuer>
2000	Access Approved	Information	File access allowed: <full_path></full_path>
			[Details]
			Access Image Path: <full_path></full_path>
			Access User: <user_name></user_name>
			Mode: <mode></mode>
			List: <list></list>

Event ID	Task Category	LEVEL	DESCRIPTION
2001	Access	Warning	File access allowed: <full_path></full_path>
	Approved		[Details]
			Access Image Path: <full_path></full_path>
			Access User: <user_name></user_name>
			Mode: <mode></mode>
2002	Access	Warning	File access allowed: <full_path></full_path>
	Approved		Unable to get the file path while checking the Approved List.
			[Details]
			Access Image Path: <full_path></full_path>
			Access User: <user_name></user_name>
			Mode: <mode></mode>
2003 Access Approved	Warning	File access allowed: <full_path></full_path>	
	Approved		Unable to calculate hash while checking the Approved List.
			[Details]
			Access Image Path: <full_path></full_path>
			Access User: <user_name></user_name>
			Mode: <mode></mode>
2004	Access	Warning	File access allowed: <full_path></full_path>
	Approved		Unable to get notifications to monitor process.
2005	Access	Warning	File access allowed: <full_path></full_path>
	Approved	Approved	Unable to add process to non exception list.

Event ID	Task Category	LEVEL	DESCRIPTION
2006	Access Approved	Information	File access allowed: <full_path></full_path>
			[Details]
			Access Image Path: <full_path></full_path>
			Access User: <user_name></user_name>
			Mode: <mode></mode>
2007	Access	Warning	File access allowed: <full_path></full_path>
	Approved		An error occurred while checking the Exception Path List.
			[Details]
			Access Image Path: <full_path></full_path>
			Access User: <user_name></user_name>
			Mode: <mode></mode>
2008	Access	Warning	File access allowed: <full_path></full_path>
	Approved		An error occurred while checking the Trusted Certificate List.
			[Details]
			Access Image Path: <full_path></full_path>
			Access User: <user_name></user_name>
			Mode: <mode></mode>

Event ID	Task Category	Level	DESCRIPTION
2011	Access	Information	Trusted registry value access allowed.
	Approved		Registry Key: <reg_key></reg_key>
			Registry Value Name: <reg_value></reg_value>
			[Details]
			Access Image Path: <full_path></full_path>
			Access User: <user_name></user_name>
			Mode: <mode></mode>
2012	Access	ed Information	Trusted registry key access allowed.
	Approved		Registry Key: <reg_key></reg_key>
			[Details]
			Access Image Path: <full_path></full_path>
			Access User: <user_name></user_name>
			Mode: <mode></mode>
2013	Access Approved	Information	Change of File/Folder allowed by Exception List: <full_path></full_path>
			[Details]
			Access Image Path: Access User: <user_name></user_name>
			Mode: <mode></mode>

Event ID	Task Category	Level	DESCRIPTION
2015	Access Approved	Information	Change of Registry Value allowed by Exception List.
			Registry Key: <reg_key></reg_key>
			Registry Value Name: <reg_value></reg_value>
			[Details]
			Access Image Path: <full_path></full_path>
			Access User: <user_name></user_name>
			Mode: <mode></mode>
2016	Access Approved	Information	Change of Registry Key allowed by Exception List.
			Registry Key: <reg_key></reg_key>
			[Details]
			Access Image Path: <full_path></full_path>
			Access User: <user_name></user_name>
			Mode: <mode></mode>
2017	Access Approved	Warning	Change of File/Folder allowed: <full_path></full_path>
			[Details]
			Access Image Path: <full_path></full_path>
			Access User: <user_name> Mode: <mode></mode></user_name>

Event ID	Task Category	Level	DESCRIPTION
2019	Access	Warning	Change of Registry Value allowed.
	Approved		Registry Key: <reg_key></reg_key>
			Registry Value Name: <reg_value></reg_value>
			[Details]
			Access Image Path: <full_path></full_path>
			Access User: <user_name></user_name>
			Mode: <mode></mode>
2020	Access	Warning	Change of Registry Key allowed.
	Approved		Registry Key: <reg_key></reg_key>
			[Details]
			Access Image Path: <full_path></full_path>
			Access User: <user_name></user_name>
			Mode: <mode></mode>
2503	Access Blocked	Warning	Change of File/Folder blocked: <full_path></full_path>
			[Details]
			Access Image Path: <full_path></full_path>
			Access User: <user_name></user_name>
			Mode: <mode></mode>

Event ID	Task Category	LEVEL	DESCRIPTION
2505	2505 Access	Warning	Change of Registry Value blocked.
	вюскеа		Registry Key: <reg_key></reg_key>
			Registry Value Name: <reg_value></reg_value>
			[Details]
			Access Image Path: <full_path></full_path>
			Access User: <user_name></user_name>
			Mode: <mode></mode>
2506	Access	Warning	Change of Registry Key blocked.
	Blocked		Registry Key: <reg_key></reg_key>
			[Details]
			Access Image Path: <full_path></full_path>
			Access User: <user_name></user_name>
			Mode: <mode></mode>
2507	Access Blocked	Information	Specified action is taken: <full_path></full_path>
			[Details]
			Action: <action></action>
			Source: <source/>
2508	Access Blocked	Warning	Failed to take specified action: <full_path></full_path>
			[Details]
			Action: <action></action>
			Source: <source/>

Event ID	Task Category	Level	DESCRIPTION
2509	Access	Warning	File access blocked: <full_path></full_path>
	BIOCKEU		[Details]
			Access Image Path: <full_path></full_path>
			Access User: <user_name></user_name>
			Mode: <mode></mode>
			Reason: Not in Approved List
2510	Access Blocked	Warning	File access blocked: <full_path></full_path>
			[Details]
			Access Image Path: <full_path></full_path>
			Access User: <user_name></user_name>
			Mode: <mode></mode>
			Reason: Hash does not match expected value
2511	Access Blocked	Information	Change of File/Folder blocked: <full_path></full_path>
			[Details]
			Access Image Path: <full_path></full_path>
			Access User: <user_name></user_name>
			Mode: <mode></mode>
3000 USB Malwa	USB Malware	Warning	Device access allowed: <full_path></full_path>
	Protection		[Details]
			Access Image Path: <full_path></full_path>
			Access User: <user_name></user_name>
			Device Type: <type></type>

Event ID	Task Category	LEVEL	DESCRIPTION
3001 USB	USB Malware	Warning	Device access blocked: <full_path></full_path>
	Protection		[Details]
			Access Image Path: <full_path></full_path>
			Access User: <user_name></user_name>
			Device Type: <type></type>
3500	Network Virus	Warning	Network virus allowed: <name></name>
	Protection		[Details]
			Protocol: TCP
			Source IP Address: <ip_address></ip_address>
			Source Port: <port></port>
			Destination IP Address: <ip_address></ip_address>
			Destination Port: <port></port>
3501	1 Network Virus Protection	Warning	Network virus blocked: <name></name>
			[Details]
			Protocol: TCP
			Source IP Address: <ip_address></ip_address>
			Source Port: <port></port>
			Destination IP Address: <ip_address></ip_address>
			Destination Port: <port></port>
4002 F	Process Protection	Warning	API Hooking allowed: <full_path></full_path>
	Event		[Details]
			Threat Image Path: <full_path></full_path>
			Threat User: <user_name></user_name>

Event ID	Task Category	LEVEL	DESCRIPTION
4003 Process	Warning	API Hooking blocked: <full_path></full_path>	
	Event		[Details]
			Threat Image Path: <full_path></full_path>
			Threat User: <user_name></user_name>
4004	Process	Warning	DLL Injection allowed: <full_path></full_path>
	Event		[Details]
			Threat Image Path: <full_path></full_path>
			Threat User: <user_name></user_name>
4005	4005 Process	Warning	DLL Injection blocked: <full_path></full_path>
	Event		[Details]
			Threat Image Path: <full_path></full_path>
			Threat User: <user_name></user_name>
4500	Changes in System	Information	File/Folder created: <full_path></full_path>
			[Details]
			Access Image Path: <full_path></full_path>
			Access Process ID: <proc_id></proc_id>
			Access User: <user_name></user_name>
4501	Changes in System	Information	File modified: <full_path></full_path>
	in Gystern		[Details]
			Access Image Path: <full_path></full_path>
			Access Process ID: <proc_id></proc_id>
			Access User: <user_name></user_name>

Event ID	Task Category	LEVEL	DESCRIPTION
4502	Changes in System	Information	File/Folder deleted: <full_path></full_path>
			[Details]
			Access Image Path: <full_path></full_path>
			Access Process ID: <proc_id></proc_id>
			Access User: <user_name></user_name>
4503	Changes	Information	File/Folder renamed: <full_path></full_path>
	in System		New path: <full_path></full_path>
			[Details]
		Access Image Path: <full_path></full_path>	
			Access Process ID: <proc_id></proc_id>
			Access User: <user_name></user_name>
4504	Changes	Information	Registry Value modified.
in System	in System		Registry Key: <reg_key></reg_key>
			Registry Value Name: <reg_value></reg_value>
			Registry Value Type: <reg_value_type></reg_value_type>
			[Details]
			Access Image Path: <full_path></full_path>
			Access Process ID: <proc_id></proc_id>
			Access User: <user_name></user_name>

Event ID	Task Category	LEVEL	DESCRIPTION
4505	4505 Changes	Information	Registry Value deleted.
	in System		Registry Key: <reg_key></reg_key>
			Registry Value Name: <reg_value></reg_value>
			[Details]
			Access Image Path: <full_path></full_path>
			Access Process ID: <proc_id></proc_id>
			Access User: <user_name></user_name>
4506	506 Changes	Information	Registry Key created.
	in System		Registry Key: <reg_key></reg_key>
			[Details]
			Access Image Path: <full_path></full_path>
			Access Process ID: <proc_id></proc_id>
			Access User: <user_name></user_name>
4507	4507 Changes in System	Information	Registry Key deleted.
			Registry Key: <reg_key></reg_key>
			[Details]
			Access Image Path: <full_path></full_path>
			Access Process ID: <proc_id></proc_id>
			Access User: <user_name></user_name>

Event ID	Task Category	Level	DESCRIPTION
4508	Changes	Information	Registry Key renamed.
in System		Registry Key: <reg_key></reg_key>	
			New Registry Key: <reg_key></reg_key>
			[Details]
			Access Image Path: <full_path></full_path>
			Access Process ID: <proc_id></proc_id>
			Access User: <user_name></user_name>

Agent Error Code Descriptions

This list describes the various error codes used in Trend Micro Safe Lock.

Code	DESCRIPTION
0x00040200	Operation successful.
0x80040201	Operation unsuccessful.
0x80040202	Operation unsuccessful.
0x00040202	Operation partially successful.
0x00040203	Requested function not installed.
0x80040203	Requested function not supported.
0x80040204	Invalid argument.
0x80040205	Invalid status.
0x80040206	Out of memory.
0x80040207	Busy. Request ignored.

Code	DESCRIPTION
0x00040208	Retry. (Usually the result of a task taking too long)
0x80040208	System Reserved. (Not used)
0x80040209	The file path is too long.
0x0004020a	System Reserved. (Not used)
0x8004020b	System Reserved. (Not used)
0x0004020c	System Reserved. (Not used)
0x0004020d	System Reserved. (Not used)
0x8004020d	System Reserved. (Not used)
0x0004020e	Reboot required.
0x8004020e	Reboot required for unexpected reason.
0x0004020f	Allowed to perform task.
0x8004020f	Permission denied.
0x00040210	System Reserved. (Not used)
0x80040210	Invalid or unexpected service mode.
0x00040211	System Reserved. (Not used)
0x80040211	Requested task not permitted in current status. Check license.
0x00040212	System Reserved. (Not used)
0x00040213	System Reserved. (Not used)
0x80040213	Passwords do not match.
0x00040214	System Reserved. (Not used)
0x80040214	System Reserved. (Not used)
0x00040215	Not found.
0x80040215	"Expected, but not found."

CODE	DESCRIPTION
0x80040216	Authentication is locked.
0x80040217	Invalid password length.
0x80040218	Invalid characters in password.
0x00040219	Duplicate password. Administrator and Restricted User passwords cannot match.
0x80040220	System Reserved. (Not used)
0x80040221	System Reserved. (Not used)
0x80040222	System Reserved. (Not used)
0x80040223	File not found (as expected, and not an error).
0x80040224	System Reserved. (Not used)
0x80040225	System Reserved. (Not used)
0x80040240	Library not found.
0x80040241	Invalid library status or unexpected error in library function.
0x80040260	System Reserved. (Not used)
0x80040261	System Reserved. (Not used)
0x80040262	System Reserved. (Not used)
0x80040263	System Reserved. (Not used)
0x80040264	System Reserved. (Not used)
0x00040265	System Reserved. (Not used)
0x80040265	System Reserved. (Not used)
0x80040270	System Reserved. (Not used)
0x80040271	System Reserved. (Not used)
0x80040272	System Reserved. (Not used)

CODE	DESCRIPTION
0x80040273	System Reserved. (Not used)
0x80040274	System Reserved. (Not used)
0x80040275	System Reserved. (Not used)
0x80040280	Invalid Activation Code.
0x80040281	Incorrect Activation Code format.



Index

A

agent configuration file, 4-2, 4-7 editing, 4-2 exporting or importing, 4-2 syntax, 4-3 agent installer approved list, 2-2 upgrade preparation, 1-9 agents, 1-2 account passwords, 2-16 accounts, 1-4, 2-15 console, 2-5 diagnostics, 5-2, 5-5, 5-6 error codes, 7-25 event ID codes, 7-4 features and benefits, 1-3 operating systems, 1-5 settings, 2-17, 2-20 status icons, 2-7 system requirements, 1-5 use overview, 1-10 Application Lockdown, 1-3 Approved List, 2-8 adding or removing files, 2-12 checking or updating hashes, 2-10 configuring, 2-11 exporting or importing, 2-14 hashes, 2-10 installing or updating files, 2-13 setting up, 2-2

С

configuration file. See agent configuration file

console feature comparison, 3-2

D

default shares, 7-3 diagnostics. *See* agents, diagnostics documentation, v

Е

error codes. *See* agents, error codes event ID codes. *See* agents, event ID codes Exploit Prevention, 1-3

Н

hashes, 2-10

I

installer. See agent installer

L

local accounts enabling administrator, 7-2 enabling default shares, 7-3 logs, 5-5

0

operating systems. See agents, operating systems

Ρ

passwords. See agents, account passwords

R

requirements. See agents, system requirements Restricted User account enabling, 2-17

S

Safe Lock. See agents Self Protection, 1-4 SLCmd Commands For Application Lockdown, 3-22 For Approved List, 3-19 For Central Management, 3-7 For Configuration File, 3-50 For General Actions, 3-4 For Optional Features, 3-9 For Predefined Trusted Updater, 3-44 For Predefined Trusted Updater "Add", 3-47 For Restricted User Accounts, 3-16 For Scripts, 3-18 For Trusted Certifications, 3-41 For Trusted Updater, 3-42 For Write Protection, 3-24 SLCmd Program, 3-3 commands. See SLCmd Commands comparison to console functions, 3-2 using, 3-2 system requirements. See agents, system requirements

Т

technical support, 6-1 Trend Micro, 6-5 Trend Micro Portable Security, 1-4, 5-2 troubleshooting. *See* agents, diagnostics Trusted Updater, 2-13

U

upgrading. See agent installer, upgrade preparation



TREND MICRO INCORPORATED

225 E. John Carpenter Freeway, Suite 1500 Irving, Texas 75062 U.S.A. Phone: +1 (817) 569-8900, Toll-free: (888) 762-8736 Email: support@treadmicro.com

